

---

# **cdrouter.py Documentation**

***Release 0.9.4***

**QA Cafe**

**Aug 03, 2023**



|          |                            |           |
|----------|----------------------------|-----------|
| <b>1</b> | <b>Introduction</b>        | <b>1</b>  |
| 1.1      | Install/Upgrade . . . . .  | 1         |
| 1.2      | Usage . . . . .            | 1         |
| <b>2</b> | <b>Reference</b>           | <b>3</b>  |
| 2.1      | CDRouter . . . . .         | 3         |
| 2.2      | Filters . . . . .          | 5         |
| 2.3      | Configs . . . . .          | 8         |
| 2.4      | Devices . . . . .          | 14        |
| 2.5      | Attachments . . . . .      | 19        |
| 2.6      | Jobs . . . . .             | 21        |
| 2.7      | Packages . . . . .         | 24        |
| 2.8      | Results . . . . .          | 29        |
| 2.9      | Alerts . . . . .           | 41        |
| 2.10     | TestResults . . . . .      | 44        |
| 2.11     | Annotations . . . . .      | 49        |
| 2.12     | Metrics . . . . .          | 51        |
| 2.13     | Captures . . . . .         | 54        |
| 2.14     | Highlights . . . . .       | 55        |
| 2.15     | Imports . . . . .          | 57        |
| 2.16     | Exports . . . . .          | 59        |
| 2.17     | History . . . . .          | 60        |
| 2.18     | System . . . . .           | 61        |
| 2.19     | Tags . . . . .             | 66        |
| 2.20     | Testsuites . . . . .       | 68        |
| 2.21     | Users . . . . .            | 74        |
|          | <b>Python Module Index</b> | <b>79</b> |
|          | <b>Index</b>               | <b>81</b> |



# CHAPTER 1

---

## Introduction

---

cdrouter is a simple Python wrapper for the CDRouter Web API. <https://support.qacafe.com/cdrouter/cdrouter-web-api/>

For more information on CDRouter, please visit <http://www.qacafe.com/>.

## 1.1 Install/Upgrade

cdrouter is available on [PyPI](#). To install the latest stable version from PyPI:

```
$ pip install -U cdrouter
```

cdrouter supports Python 3.5 or newer.

## 1.2 Usage

First create a *CDRouter* object, passing it the URL of your CDRouter system, for example `http://localhost`, `https://cdrouter.example.com` or `http://172.20.0.1:8015`. If your CDRouter system uses a self-signed certificate for HTTPS connections (the default), you will need to pass in `insecure=True` to disable certificate validation. If Automatic Login is not enabled on your CDRouter system, you will need to provide authentication credentials by passing in an API token via the `token` parameter or a username and password via the `username` and `password` parameters. If `token` is not specified, it will default to the value of the `CDROUTER_API_TOKEN` environment variable. *CDRouter* will prompt for a username and password as necessary if Automatic Login is not enabled and an API token is not provided.

```
import time

from cdrouter import CDRouter
from cdrouter.cdrouter import CDRouterError
from cdrouter.filters import Field as field
```

(continues on next page)

(continued from previous page)

```
from cdrouter.jobs import Job
from cdrouter.jobs import Options

c = CDRouter('http://localhost', token='deadbeef')

for p in c.packages.iter_list(filter=field('tags').contains('noretry')):
    print('Launching package {}'.format(p.name))

    try:
        j = c.jobs.launch(Job(package_id=p.id, options=Options(extra_cli_args='--
→testvar myvar=example'))
    except CDRouterError as ce:
        print('Error launching job: {}'.format(ce))
        continue

    while j.result_id == None:
        time.sleep(1)
        j = c.jobs.get(j.id)

    print('    Result-ID: {}'.format(j.result_id))

print('done.')
```

More examples of using cdrouter can be found [here](#). Please see the *Reference* page for more information on available fields and methods for each class.

Python client for the CDRouter Web API.

## 2.1 CDRouter

### 2.1.1 CDRouter

```
class cdrouter.CDRouter(base, token=None, username=None, password=None, _getuser=<function  
_getuser_default>, _getpass=<function _getpass_default>, retries=3, in-  
secure=False)
```

Service for accessing the CDRouter Web API.

#### Parameters

- **base** – Base HTTP or HTTPS URL for CDRouter system as a string, optionally including a port. For example *http://localhost*, *http://cdrouter.lan:8015* or *https://127.0.0.1*.
- **token** – (optional) CDRouter API token as a string. Not required if Automatic Login is enabled. If omitted, value will be taken from CDRouter\_API\_TOKEN environment variable.
- **username** – (optional) Username as string. Can be omitted if **token** is specified or Automatic Login is enabled. If omitted, `_getuser` will be called when a username is required.
- **password** – (optional) Password as string. Can be omitted if **token** is specified or Automatic Login is enabled. If omitted, `_getpass` will be called when a password is required.
- **\_getuser** – (optional) If **username** is *None*, function to be called as `_getuser(base)` which returns a username as a string. If `_getuser` is *None*, `cdrouter` will print a prompt to stdout and read the username from stdin.
- **\_getpass** – (optional) If **password** is *None*, a function to be called as `_getpass(base, username)` which returns user's password as a string. If `_getpass` is *None*, `cdrouter` will print a password prompt to stdout and read the password from stdin.

- **retries** – (optional) The number of times to retry authentication with the CDRouter system before giving up as an int.
- **insecure** – (optional) If bool *True* and *base* is an HTTPS URL, skip certificate verification and allow insecure connections to the CDRouter system.

**alerts = None**

*alerts.AlertsService* object

**annotations = None**

*annotations.AnnotationsService* object

**attachments = None**

*attachments.AttachmentsService* object

**authenticate** (*retries=3*)

Set API token by authenticating via username/password.

**Parameters** **retries** – Number of authentication retries to make before giving up as an int.

**Returns** Learned API token

**Return type** string

**captures = None**

*captures.CapturesService* object

**configs = None**

*configs.ConfigsService* object

**devices = None**

*devices.DevicesService* object

**exports = None**

*exports.ExportsService* object

**highlights = None**

*highlights.HighlightsService* object

**history = None**

*history.HistoryService* object

**imports = None**

*imports.ImportsService* object

**jobs = None**

*jobs.JobsService* object

**packages = None**

*packages.PackagesService* object

**results = None**

*results.ResultsService* object

**system = None**

*system.SystemService* object

**tags = None**

*tags.TagsService* object

**tests = None**

*testresults.TestResultsService* object

**testsuites = None**

*testsuites.TestsuitesService* object



```
users = None
users.UsersService object
```

## 2.1.2 CDRouterError

```
class cdrouter.cdrouter.CDRouterError(*args, **kwargs)
    Class for representing CDRouter Web API errors.
```

## 2.1.3 Links

```
class cdrouter.cdrouter.Links(**kwargs)
    Class representing paging information returned by list calls to the CDRouter Web API.
```

### Parameters

- **first** – (optional) First page number as an int.
- **last** – (optional) Last page number as an int.
- **current** – (optional) Current page number as an int.
- **total** – (optional) Total element count across all pages as an int.
- **limit** – (optional) Resources per page limit as an int.
- **next** – (optional) Next page number as an int.
- **prev** – (optional) Previous page number as an int.

## 2.1.4 Share

```
class cdrouter.cdrouter.Share(**kwargs)
    Model for CDRouter Shares.
```

### Parameters

- **user\_id** – (optional) User ID as an int.
- **read** – (optional) Bool *True* if reading is allowed.
- **write** – (optional) Bool *True* if writing is allowed.
- **execute** – (optional) Bool *True* if executing is allowed.

## 2.2 Filters

### 2.2.1 Field

```
class cdrouter.filters.Field(*args)
    Class for constructing CDRouter Web API filters. Field objects can be passed to filter parameters to make constructing filters easier.
```

The `value` parameter passed to Field methods is converted to a string using the builtin `str` function. Bool values are additionally lowercased such that bool `True` becomes string `'true'` and `False` becomes string `'false'`. The Field methods `contains`, `contained_by` and `overlaps` accept a variable number of values which are converted into a list in accordance with the API's syntax. For example, the int values `1, 2,`

3 is converted to the string '{1,2,3}' and the string values 'one', 'two', 'three' is converted to the string '{one,two,three}'.

Usage:

```
from cdrouter.filters import Field as field
# each pair of filters below are equivalent
c.packages.list(filter=[
    field('id').eq(123),
    'id=123',
    #
    field('use_as_testlist').ne(True),
    'use_as_testlist!=true',
    #
    field('name').not_().match('^(foo|bar)$', ignorecase=True),
    'name!~*(foo|bar)$',
    #
    field('tags').contains('foo', 'bar', 'baz'),
    'tags@>{foo,bar,baz}',
])
```

See [this](#) page for more details on CDRouter Web API filters.

**contained\_by** (\*args)

Construct an array contained by (<@) filter.

**Parameters** **args** – Filter values

**Returns** `filters.Field` object

**Return type** *filters.Field*

**contains** (\*args)

Construct an array contains (@>) filter.

**Parameters** **args** – Filter values

**Returns** `filters.Field` object

**Return type** *filters.Field*

**eq** (value)

Construct an equal to (=) filter.

**Parameters** **value** – Filter value

**Returns** `filters.Field` object

**Return type** *filters.Field*

**ge** (value)

Construct a greater than or equal to (>=) filter.

**Parameters** **value** – Filter value

**Returns** `filters.Field` object

**Return type** *filters.Field*

**gt** (value)

Construct a greater than (>) filter.

**Parameters** **value** – Filter value

**Returns** `filters.Field` object

**Return type** *filters.Field*

**le** (*value*)

Construct a less than or equal to ( $\leq$ ) filter.

**Parameters** **value** – Filter value

**Returns** *filters.Field* object

**Return type** *filters.Field*

**lt** (*value*)

Construct a less than ( $<$ ) filter.

**Parameters** **value** – Filter value

**Returns** *filters.Field* object

**Return type** *filters.Field*

**match** (*value*, *ignorecase=False*)

Construct a regexp match ( $\sim$ ) filter. Combine with `not_` method to construct a negative regexp match ( $!\sim$ ) filter.

**Parameters**

- **value** – Filter value
- **ignorecase** – If bool *True*, make match case insensitive ( $\sim^*$ ,  $!\sim^*$ )

**Returns** *filters.Field* object

**Return type** *filters.Field*

**ne** (*value*)

Construct a not equal to ( $\neq$ ) filter.

**Parameters** **value** – Filter value

**Returns** *filters.Field* object

**Return type** *filters.Field*

**not\_** ()

Negate the filter. Not supported by `contains`, `contained_by` or `overlaps` methods.

**Returns** *filters.Field* object

**Return type** *filters.Field*

**overlaps** (*\*args*)

Construct an array overlaps ( $\&\&$ ) filter.

**Parameters** **args** – Filter values

**Returns** *filters.Field* object

**Return type** *filters.Field*

## 2.3 Configs

### 2.3.1 ConfigsService

**class** `cdrouter.configs.ConfigsService` (*service*)

Service for accessing CDRouter Configs.

**bulk\_copy** (*ids*)

Bulk copy a set of configs.

**Parameters** *ids* – Int list of config IDs.

**Returns** `configs.Config` list

**bulk\_delete** (*ids=None, filter=None, type=None, all=False*)

Bulk delete a set of configs.

**Parameters**

- *ids* – (optional) Int list of config IDs.
- *filter* – (optional) String list of filters.
- *type* – (optional) *union* or *inter* as string.
- *all* – (optional) Apply to all if bool *True*.

**bulk\_edit** (*\_fields, ids=None, filter=None, type=None, all=False, testvars=None*)

Bulk edit a set of configs.

**Parameters**

- *\_fields* – `configs.Config` object
- *ids* – (optional) Int list of config IDs.
- *filter* – (optional) String list of filters.
- *type* – (optional) *union* or *inter* as string.
- *all* – (optional) Apply to all if bool *True*.
- *testvars* – (optional) `configs.ConfigTestvars` list

**bulk\_edit\_testvars** (*id, testvars*)

Bulk edit a config's testvars.

**Parameters**

- *id* – Config ID as an int.
- *testvars* – `configs.Testvar` list

**Returns** `configs.Testvar` list

**bulk\_export** (*ids*)

Bulk export a set of configs.

**Parameters** *ids* – Int list of config IDs.

**Return type** tuple (*io.BytesIO*, *'filename'*)

**bulk\_upgrade** (*ids=None, filter=None, type=None, all=False*)

Bulk upgrade a set of configs.

**Parameters**

- **ids** – (optional) Int list of config IDs.
- **filter** – (optional) String list of filters.
- **type** – (optional) *union* or *inter* as string.
- **all** – (optional) Apply to all if bool *True*.

**check\_config** (*contents*)

Process config contents with cdrouter-cli -check-config.

**Parameters** **contents** – Config contents as string.

**Returns** `configs.CheckConfig` object

**Return type** `configs.CheckConfig`

**create** (*resource*)

Create a new config.

**Parameters** **resource** – `configs.Config` object

**Returns** `configs.Config` object

**Return type** `configs.Config`

**create\_testvar\_group** (*id*, *group*)

Create a testvar group in a config. Creating a testvar group is equivalent to removing the IGNORE keyword from the group in the config.

**Parameters**

- **id** – Config ID as an int.
- **group** – Testvar group as string.

**delete** (*id*)

Delete a config.

**Parameters** **id** – Config ID as an int.

**delete\_testvar** (*id*, *name*, *group=None*)

Delete a testvar in a config. Deleting a testvar unsets any explicitly configured value for it in the config.

**Parameters**

- **id** – Config ID as an int.
- **name** – Testvar name as string.
- **group** – (optional) Testvar group as string.

**delete\_testvar\_group** (*id*, *group*)

Delete a testvar group in a config. Deleting a testvar group is equivalent to adding the IGNORE keyword to the group in the config.

**Parameters**

- **id** – Config ID as an int.
- **group** – Testvar group as string.

**edit** (*resource*)

Edit a config.

**Parameters** **resource** – `configs.Config` object

**Returns** `configs.Config` object

**Return type** *configs.Config*

**edit\_shares** (*id*, *user\_ids*)

Edit shares for a config.

**Parameters**

- **id** – Config ID as an int.
- **user\_ids** – User IDs as int list.

**Returns** *cdrouter.Share* list

**edit\_testvar** (*id*, *resource*)

Edit a testvar in a config.

**Parameters**

- **id** – Config ID as an int.
- **resource** – *configs.Testvar* object.

**Returns** *configs.Testvar* object

**Return type** *configs.Testvar*

**export** (*id*)

Export a config.

**Parameters** **id** – Config ID as an int.

**Return type** tuple (*io.BytesIO*, 'filename')

**get** (*id*)

Get a config.

**Parameters** **id** – Config ID as an int.

**Returns** *configs.Config* object

**Return type** *configs.Config*

**get\_by\_name** (*name*)

Get a config by name.

**Parameters** **name** – Config name as string.

**Returns** *configs.Config* object

**Return type** *configs.Config*

**get\_interfaces** (*contents*)

Process config contents with *cdrouter-cli -print-interfaces*.

**Parameters** **contents** – Config contents as string.

**Returns** *configs.Interfaces* list

**get\_networks** (*contents*)

Process config contents with *cdrouter-cli -print-networks-json*.

**Parameters** **contents** – Config contents as string.

**Returns** *configs.Networks* object

**Return type** *configs.Networks*

**get\_new** ()

Get output of *cdrouter-cli -new-config*.

**Return type** string

**get\_plaintext** (*id*)

Get a config as plaintext.

**Parameters** *id* – Config ID as an int.

**Return type** string

**get\_shares** (*id*)

Get shares for a config.

**Parameters** *id* – Config ID as an int.

**Returns** `cdrouter.Share` list

**get\_testvar** (*id*, *name*, *group=None*)

Get a testvar from a config.

**Parameters**

- *id* – Config ID as an int.
- *name* – Testvar name as string.
- *group* – (optional) Testvar group as string.

**Returns** `configs.Testvar` object

**Return type** `configs.Testvar`

**iter\_list** (*\*args*, *\*\*kwargs*)

Get a list of configs. Whereas `list` fetches a single page of configs according to its `limit` and `page` arguments, `iter_list` returns all configs by internally making successive calls to `list`.

**Parameters**

- *args* – Arguments that `list` takes.
- *kwargs* – Optional arguments that `list` takes.

**Returns** `configs.Config` list

**list** (*filter=None*, *type=None*, *sort=None*, *limit=None*, *page=None*, *detailed=None*)

Get a list of configs, using summary representation by default (see `detailed` parameter).

**Parameters**

- *filter* – (optional) Filters to apply as a string list.
- *type* – (optional) *union* or *inter* as string.
- *sort* – (optional) Sort fields to apply as string list.
- *limit* – (optional) Limit returned list length.
- *page* – (optional) Page to return.
- *detailed* – (optional) Return all fields if Bool *True*.

**Returns** `configs.Page` object

**list\_testvars** (*id*)

Get a list of a config's testvars.

**Parameters** *id* – Config ID as an int.

**Returns** `configs.Testvar` list

**lock** (*id*)

Lock a config. Locking prevents the config from being modified or deleted until it is unlocked.

**Parameters** **id** – Config ID as an int.

**Returns** `configs.Config` object

**Return type** `configs.Config`

**unlock** (*id*)

Unlock a config. Unlocking a locked config allows it to be modified or deleted once again.

**Parameters** **id** – Config ID as an int.

**Returns** `configs.Config` object

**Return type** `configs.Config`

**upgrade\_config** (*contents*)

Process config contents with `cdrouter-cli -upgrade-config`.

**Parameters** **contents** – Config contents as string.

**Returns** `configs.UpgradeConfig` object

**Return type** `configs.UpgradeConfig`

## 2.3.2 Config

**class** `cdrouter.configs.Config` (**\*\*kwargs**)

Model for CDRouter Configs.

**Parameters**

- **id** – (optional) Config ID as an int.
- **name** – (optional) Config name as string.
- **description** – (optional) Config description as string.
- **created** – (optional) Creation time as *DateTime*.
- **updated** – (optional) Last-updated time as *DateTime*.
- **locked** – (optional) Bool *True* if config is locked.
- **contents** – (optional) Config contents as string.
- **user\_id** – (optional) User ID as an int.
- **result\_id** – (optional) Result ID as an int (if a config snapshot).
- **tags** – (optional) Tags as string list.
- **note** – (optional) Note as string.
- **interfaces** – (optional) `configs.Interfaces` list (if a config snapshot).

## 2.3.3 Page

**class** `cdrouter.configs.Page`

Named tuple for a page of list response data.

**Parameters**



- **data** – `configs.Config` list
- **links** – `cdrouter.Links` object

### 2.3.4 ConfigError

**class** `cdrouter.configs.ConfigError` (*\*\*kwargs*)  
Model for CDRouter Check Config Error.

**Parameters**

- **lines** – (optional) Line numbers as string list.
- **error** – (optional) Error message as string.

### 2.3.5 CheckConfig

**class** `cdrouter.configs.CheckConfig` (*\*\*kwargs*)  
Model for CDRouter Check Config.

**Parameters** **errors** – (optional) `configs.ConfigError` list

### 2.3.6 UpgradeConfig

**class** `cdrouter.configs.UpgradeConfig` (*\*\*kwargs*)  
Model for CDRouter Config Upgrades.

**Parameters**

- **success** – (optional) Bool *True* if successful.
- **output** – (optional) Output as string.

### 2.3.7 Networks

**class** `cdrouter.configs.Networks` (*\*\*kwargs*)  
Model for CDRouter Config Networks.

**Parameters**

- **name** – (optional) Network name as string.
- **type** – (optional) Network type as string.
- **side** – (optional) Network side as string.
- **title** – (optional) Network title as string.
- **children** – (optional) `configs.Networks` list.

### 2.3.8 Interfaces

**class** `cdrouter.configs.Interfaces` (*\*\*kwargs*)  
Model for CDRouter Config Interfaces.

**Parameters**

- **name** – (optional) Interface name (i.e. 'lan', 'wan', etc.) as string.

- **value** – (optional) Interface value (i.e. ‘eth0’, ‘eth1’, etc.) as string.
- **is\_wireless** – (optional) Bool *True* if interface is a wireless interface.
- **is\_ics** – (optional) Bool *True* if interface is the ICS interface.

## 2.3.9 Testvar

**class** `cdrouter.configs.Testvar` (*\*\*kwargs*)  
Model for CDRouter Config Testvars.

### Parameters

- **group** – (optional) Testvar group name as string.
- **name** – (optional) Testvar name as string.
- **value** – (optional) Testvar value as string.
- **default** – (optional) Testvar default value as string.
- **isdefault** – (optional) Bool *True* if testvar is set to default value.
- **line** – (optional) Config file line number as int.
- **action** – (optional) Action to perform on the testvar or group as string. Must be *set-testvar*, *delete-testvar*, *create-group* or *delete-group*. If not specified, defaults to *set-testvar*.

## 2.4 Devices

### 2.4.1 DevicesService

**class** `cdrouter.devices.DevicesService` (*service*)  
Service for accessing CDRouter Devices.

**bulk\_copy** (*ids*)  
Bulk copy a set of devices.

**Parameters** **ids** – Int list of device IDs.

**Returns** `devices.Device` list

**bulk\_delete** (*ids=None, filter=None, type=None, all=False*)  
Bulk delete a set of devices.

### Parameters

- **ids** – (optional) Int list of device IDs.
- **filter** – (optional) String list of filters.
- **type** – (optional) *union* or *inter* as string.
- **all** – (optional) Apply to all if bool *True*.

**bulk\_edit** (*\_fields, ids=None, filter=None, type=None, all=False*)  
Bulk edit a set of devices.

### Parameters

- **\_fields** – `devices.Device` object
- **ids** – (optional) Int list of device IDs.

- **filter** – (optional) String list of filters.
- **type** – (optional) *union* or *inter* as string.
- **all** – (optional) Apply to all if bool *True*.

**bulk\_export** (*ids*)

Bulk export a set of devices.

**Parameters** **ids** – Int list of device IDs.

**Return type** tuple (*io.BytesIO*, *'filename'*)

**connect** (*id*)

Open proxy connection to a device's management interface.

**Parameters** **id** – Device ID as an int.

**Returns** *devices.Connection* object

**Return type** *devices.Connection*

**create** (*resource*)

Create a new device.

**Parameters** **resource** – *devices.Device* object

**Returns** *devices.Device* object

**Return type** *devices.Device*

**delete** (*id*)

Delete a device.

**Parameters** **id** – Device ID as an int.

**disconnect** (*id*)

Close proxy connection to a device's management interface.

**Parameters** **id** – Device ID as an int.

**edit** (*resource*)

Edit a device.

**Parameters** **resource** – *devices.Device* object

**Returns** *devices.Device* object

**Return type** *devices.Device*

**edit\_shares** (*id, user\_ids*)

Edit shares for a device.

**Parameters**

- **id** – Device ID as an int.
- **user\_ids** – User IDs as int list.

**Returns** *cdrouter.Share* list

**export** (*id*)

Export a device.

**Parameters** **id** – Device ID as an int.

**Return type** tuple (*io.BytesIO*, *'filename'*)

**get** (*id*)

Get a device.

**Parameters** *id* – Device ID as an int.

**Returns** `devices.Device` object

**Return type** `devices.Device`

**get\_by\_name** (*name*)

Get a device by name.

**Parameters** *name* – Device name as string.

**Returns** `devices.Device` object

**Return type** `devices.Device`

**get\_connection** (*id*)

Get information on proxy connection to a device's management interface.

**Parameters** *id* – Device ID as an int.

**Returns** `devices.Connection` object

**Return type** `devices.Connection`

**get\_shares** (*id*)

Get shares for a device.

**Parameters** *id* – Device ID as an int.

**Returns** `cdrouter.Share` list

**iter\_list** (\**args*, \*\**kwargs*)

Get a list of devices. Whereas `list` fetches a single page of devices according to its `limit` and `page` arguments, `iter_list` returns all devices by internally making successive calls to `list`.

**Parameters**

- **args** – Arguments that `list` takes.
- **kwargs** – Optional arguments that `list` takes.

**Returns** `devices.Device` list

**list** (*filter=None, type=None, sort=None, limit=None, page=None, detailed=None*)

Get a list of devices, using summary representation by default (see `detailed` parameter).

**Parameters**

- **filter** – (optional) Filters to apply as a string list.
- **type** – (optional) *union* or *inter* as string.
- **sort** – (optional) Sort fields to apply as string list.
- **limit** – (optional) Limit returned list length.
- **page** – (optional) Page to return.
- **detailed** – (optional) Return all fields if Bool *True*.

**Returns** `devices.Page` object

**lock** (*id*)

Lock a device. Locking prevents the device from being modified or deleted until it is unlocked.

**Parameters** *id* – Device ID as an int.

**Returns** `devices.Device` object

**Return type** `devices.Device`

**power\_off** (*id*)

Power off a device using it's power off command.

**Parameters** *id* – Device ID as an int.

**Returns** `devices.PowerCmd` object

**Return type** `devices.PowerCmd`

**power\_on** (*id*)

Power on a device using it's power on command.

**Parameters** *id* – Device ID as an int.

**Returns** `devices.PowerCmd` object

**Return type** `devices.PowerCmd`

**unlock** (*id*)

Unlock a device. Unlocking a locked device allows it to be modified or deleted once again.

**Parameters** *id* – Device ID as an int.

**Returns** `devices.Device` object

**Return type** `devices.Device`

## 2.4.2 Device

**class** `cdrouter.devices.Device` (*\*\*kwargs*)  
Model for CDRouter Devices.

### Parameters

- **id** – (optional) Device ID as an int.
- **name** – (optional) Name as string.
- **created** – (optional) Creation time as *DateTime*.
- **updated** – (optional) Last-updated time as *DateTime*.
- **locked** – (optional) Bool *True* if device is locked.
- **user\_id** – (optional) User ID as an int.
- **result\_id** – (optional) Result ID as an int (if a device snapshot).
- **attachments\_dir** – (optional) Filepath for attachments as string.
- **picture\_id** – (optional) Attachment ID for used for device picture as an int.
- **tags** – (optional) Tags as string list.
- **default\_ip** – (optional) Default IP as a string
- **default\_login** – (optional) Default login as a string
- **default\_password** – (optional) Default password as a string
- **default\_ssid** – (optional) Default SSID as a string
- **location** – (optional) Location as a string

- **device\_category** – (optional) Device category as a string
- **manufacturer** – (optional) Manufacturer as a string
- **manufacturer\_oui** – (optional) Manufacturer OUI as a string
- **model\_name** – (optional) Model name as a string
- **model\_number** – (optional) Model number as a string
- **description** – (optional) Description as a string
- **product\_class** – (optional) Product class as a string
- **serial\_number** – (optional) Serial number as a string
- **hardware\_version** – (optional) Hardware version as a string
- **software\_version** – (optional) Software version as a string
- **provisioning\_code** – (optional) Provisioning code as a string
- **note** – (optional) Note as a string
- **insecure\_mgmt\_url** – (optional) *True* if insecure HTTPS management URLs are allowed
- **mgmt\_url** – (optional) Management URL as a string
- **add\_mgmt\_addr** – (optional) *True* if address should be configured when opening proxy connection
- **mgmt\_interface** – (optional) Interface on which to configure address as string
- **mgmt\_addr** – (optional) Address to configure as string
- **power\_on\_cmd** – (optional) Command to run to power on device as string
- **power\_off\_cmd** – (optional) Command to run to power off device as string

### 2.4.3 Page

**class** cdrouter.devices.**Page**

Named tuple for a page of list response data.

**Parameters**

- **data** – `devices.Device` list
- **links** – `cdrouter.Links` object

### 2.4.4 PowerCmd

**class** cdrouter.devices.**PowerCmd** (*\*\*kwargs*)

Model for CDRouter Device Power command result.

**Parameters** **output** – (optional) Output from power on/off command as string.

## 2.4.5 Connection

**class** `cdrouter.devices.Connection` (*\*\*kwargs*)  
Model for CDRouter Device Connections.

### Parameters

- **proxy\_port** – (optional) HTTP proxy port as an int.
- **proxy\_https** – (optional) HTTPS proxy port as an int.

## 2.5 Attachments

### 2.5.1 AttachmentsService

**class** `cdrouter.attachments.AttachmentsService` (*service*)

**create** (*id, fd, filename='attachment-name'*)  
Add an attachment to a device.

### Parameters

- **id** – Device ID as an int.
- **fd** – File-like object to upload.
- **filename** – (optional) Name to use for new attachment as a string.

**Returns** `attachments.Attachment` object

**Return type** `attachments.Attachment`

**delete** (*id, attid*)  
Delete a device's attachment.

### Parameters

- **id** – Device ID as an int.
- **attid** – Attachment ID as an int.

**download** (*id, attid*)  
Download a device's attachment.

### Parameters

- **id** – Device ID as an int.
- **attid** – Attachment ID as an int.

**Return type** tuple (*io.BytesIO, 'filename'*)

**edit** (*resource*)  
Edit a device's attachment.

**Parameters** **resource** – `attachments.Attachment` object

**Returns** `attachments.Attachment` object

**Return type** `attachments.Attachment`

**get** (*id, attid*)  
Get a device's attachment.

**Parameters**

- **id** – Device ID as an int.
- **attid** – Attachment ID as an int.

**Returns** `attachments.Attachment` object

**Return type** `attachments.Attachment`

**iter\_list** (*id*, \**args*, \*\**kwargs*)

Get a list of attachments. Whereas `list` fetches a single page of attachments according to its `limit` and `page` arguments, `iter_list` returns all attachments by internally making successive calls to `list`.

**Parameters**

- **id** – Device ID as an int.
- **args** – Arguments that `list` takes.
- **kwargs** – Optional arguments that `list` takes.

**Returns** `attachments.Attachment` list

**list** (*id*, *filter=None*, *type=None*, *sort=None*, *limit=None*, *page=None*, *detailed=None*)

Get a list of a device's attachments, using summary representation by default (see `detailed` parameter).

**Parameters**

- **id** – Device ID as an int.
- **filter** – (optional) Filters to apply as a string list.
- **type** – (optional) *union* or *inter* as string.
- **sort** – (optional) Sort fields to apply as string list.
- **limit** – (optional) Limit returned list length.
- **page** – (optional) Page to return.
- **detailed** – (optional) Return all fields if Bool *True*.

**Returns** `attachments.Page` object

**thumbnail** (*id*, *attid*, *size=None*)

Download thumbnail of a device's attachment. Attachment must be a GIF, JPEG or PNG image.

**Parameters**

- **id** – Device ID as an int.
- **attid** – Attachment ID as an int.
- **size** – (optional) Height in pixels of generated thumbnail.

**Return type** tuple (*io.BytesIO*, *'filename'*)

## 2.5.2 Attachment

**class** `cdrouter.attachments.Attachment` (\*\**kwargs*)

Model for CDRouter Attachments.

**Parameters**

- **id** – (optional) Attachment ID as an int.
- **name** – (optional) Name as string.



- **description** – (optional) Description as string.
- **created** – (optional) Creation time as *DateTime*.
- **updated** – (optional) Last-updated time as *DateTime*.
- **size** – (optional) Attachment size as an int.
- **path** – (optional) Filepath to attachment as string.
- **device\_id** – (optional) Device ID as an int.

### 2.5.3 Page

**class** `cdrouter.attachments.Page`

Named tuple for a page of list response data.

#### Parameters

- **data** – `attachments.Attachment` list
- **links** – `cdrouter.Links` object

## 2.6 Jobs

### 2.6.1 JobsService

**class** `cdrouter.jobs.JobsService` (*service*)

Service for accessing CDRouter Jobs.

**bulk\_delete** (*ids=None, filter=None, type=None, all=False*)

Bulk delete a set of jobs.

#### Parameters

- **ids** – (optional) Int list of job IDs.
- **filter** – (optional) String list of filters.
- **type** – (optional) *union* or *inter* as string.
- **all** – (optional) Apply to all if bool *True*.

**bulk\_launch** (*jobs=None, \_fields=None, filter=None, type=None, all=False*)

Bulk launch a set of jobs.

#### Parameters

- **jobs** – `jobs.Job` list
- **\_fields** – `jobs.Job` object
- **filter** – (optional) Filters to apply as a string list.
- **type** – (optional) *union* or *inter* as string.
- **all** – (optional) Apply to all if bool *True*.

**Returns** `jobs.Job` list

**delete** (*id*)

Delete a job.

**Parameters** `id` – Job ID as an int.

**edit** (*resource*)

Edit a job.

**Parameters** `resource` – `jobs.Job` object

**Returns** `jobs.Job` object

**Return type** *jobs.Job*

**get** (*id*)

Get a job.

**Parameters** `id` – Job ID as an int.

**Returns** `jobs.Job` object

**Return type** *jobs.Job*

**get\_interfaces** (*resource*)

Process job with `cdrouter-cli -print-interfaces`.

**Parameters** `resource` – `jobs.Job` object

**Returns** `configs.Interfaces` list

**iter\_list** (*\*args, \*\*kwargs*)

Get a list of jobs. Whereas `list` fetches a single page of jobs according to its `limit` and `page` arguments, `iter_list` returns all jobs by internally making successive calls to `list`.

**Parameters**

- **args** – Arguments that `list` takes.
- **kwargs** – Optional arguments that `list` takes.

**Returns** `jobs.Job` list

**launch** (*resource*)

Launch a new job.

**Parameters** `resource` – `jobs.Job` object

**Returns** `jobs.Job` object

**Return type** *jobs.Job*

**list** (*filter=None, type=None, sort=None, limit=None, page=None, detailed=None*)

Get a list of jobs, using summary representation by default (see `detailed` parameter).

**Parameters**

- **filter** – (optional) Filters to apply as a string list.
- **type** – (optional) *union* or *inter* as string.
- **sort** – (optional) Sort fields to apply as string list.
- **limit** – (optional) Limit returned list length.
- **page** – (optional) Page to return.
- **detailed** – (optional) Return all fields if Bool *True*.

**Returns** `jobs.Page` object

## 2.6.2 Job

**class** cdrouter.jobs.**Job** (\*\*kwargs)  
Model for CDRouter Jobs.

### Parameters

- **id** – (optional) Job ID as an int.
- **active** – (optional) Bool *True* if status is ‘running’.
- **status** – (optional) Job status as a string.
- **options** – (optional) jobs.Options object
- **package\_id** – (optional) Package ID as an int.
- **package\_name** – (optional) Package name as string.
- **config\_id** – (optional) Config ID as an int.
- **config\_name** – (optional) Config name as string.
- **device\_id** – (optional) Device ID as an int.
- **device\_name** – (optional) Device name as string.
- **result\_id** – (optional) Result ID as an int.
- **user\_id** – (optional) User ID as an int.
- **created** – (optional) Job creation time as *DateTime*.
- **updated** – (optional) Job last-updated time as *DateTime*.
- **automatic** – (optional) Bool *True* if job scheduled automatically *DateTime*.
- **run\_at** – (optional) Job scheduled run-time *DateTime*.
- **interfaces** – (optional) configs.Interfaces list
- **interface\_names** – (optional) Job interface names as string list.
- **uses\_wireless** – (optional) Bool *True* if job uses any wireless interfaces.
- **uses\_ics** – (optional) Bool *True* if job uses any ICS interfaces.
- **ics\_interface\_name** – (optional) If uses\_ics is *True*, ICS interface name as string.

## 2.6.3 Options

**class** cdrouter.jobs.**Options** (\*\*kwargs)  
Model for CDRouter Job Options.

### Parameters

- **tags** – (optional) Tags as string list.
- **skip\_tests** – (optional) Tests to skip as string list.
- **begin\_at** – (optional) Test name to begin testing at as string.
- **end\_at** – (optional) Test name to end testing at as string.
- **testvars** – (optional) Extra testvars to set as a configs.Testvar list.
- **extra\_cli\_args** – (optional) Extra *cdrouter-cli* arguments as string.

## 2.6.4 Page

**class** `cdrouter.jobs.Page`

Named tuple for a page of list response data.

**Parameters**

- **data** – `jobs.Job` list
- **links** – `cdrouter.Links` object

## 2.7 Packages

### 2.7.1 PackagesService

**class** `cdrouter.packages.PackagesService` (*service*)

Service for accessing CDRouter Packages.

**analyze** (*id*)

Get a list of tests that will be skipped for a package.

**Parameters** **id** – Package ID as an int.

**Returns** `packages.Analysis` object

**Return type** *`packages.Analysis`*

**bulk\_copy** (*ids*)

Bulk copy a set of packages.

**Parameters** **ids** – Int list of package IDs.

**Returns** `packages.Package` list

**bulk\_delete** (*ids=None, filter=None, type=None, all=False*)

Bulk delete a set of packages.

**Parameters**

- **ids** – (optional) Int list of package IDs.
- **filter** – (optional) String list of filters.
- **type** – (optional) *union* or *inter* as string.
- **all** – (optional) Apply to all if bool *True*.

**bulk\_edit** (*\_fields, ids=None, filter=None, type=None, all=False*)

Bulk edit a set of packages.

**Parameters**

- **\_fields** – `packages.Package` object
- **ids** – (optional) Int list of package IDs.
- **filter** – (optional) String list of filters.
- **type** – (optional) *union* or *inter* as string.
- **all** – (optional) Apply to all if bool *True*.

**bulk\_export** (*ids*)

Bulk export a set of packages.

**Parameters** `ids` – Int list of package IDs.

**Return type** tuple (*io.BytesIO*, 'filename')

**create** (*resource*)

Create a new package.

**Parameters** `resource` – `packages.Package` object

**Returns** `packages.Package` object

**Return type** *packages.Package*

**delete** (*id*)

Delete a package.

**Parameters** `id` – Package ID as an int.

**edit** (*resource*)

Edit a package.

**Parameters** `resource` – `packages.Package` object

**Returns** `packages.Package` object

**Return type** *packages.Package*

**edit\_shares** (*id*, *user\_ids*)

Edit shares for a package.

**Parameters**

- `id` – Package ID as an int.
- `user_ids` – User IDs as int list.

**Returns** `cdrouter.Share` list

**export** (*id*)

Export a package.

**Parameters** `id` – Package ID as an int.

**Return type** tuple (*io.BytesIO*, 'filename')

**get** (*id*)

Get a package.

**Parameters** `id` – Package ID as an int.

**Returns** `packages.Package` object

**Return type** *packages.Package*

**get\_by\_name** (*name*)

Get a package by name.

**Parameters** `name` – Package name as string.

**Returns** `packages.Package` object

**Return type** *packages.Package*

**get\_interfaces** (*resource*)

Process package with `cdrouter-cli -print-interfaces`.

**Parameters** `resource` – `packages.Package` object

**Returns** `configs.Interfaces` list

**get\_shares** (*id*)

Get shares for a package.

**Parameters** *id* – Package ID as an int.

**Returns** `cdrouter.Share` list

**iter\_list** (\**args*, \*\**kwargs*)

Get a list of packages. Whereas `list` fetches a single page of packages according to its `limit` and `page` arguments, `iter_list` returns all packages by internally making successive calls to `list`.

**Parameters**

- **args** – Arguments that `list` takes.
- **kwargs** – Optional arguments that `list` takes.

**Returns** `packages.Package` list

**list** (*filter=None*, *type=None*, *sort=None*, *limit=None*, *page=None*, *detailed=None*)

Get a list of packages, using summary representation by default (see `detailed` parameter).

**Parameters**

- **filter** – (optional) Filters to apply as a string list.
- **type** – (optional) *union* or *inter* as string.
- **sort** – (optional) Sort fields to apply as string list.
- **limit** – (optional) Limit returned list length.
- **page** – (optional) Page to return.
- **detailed** – (optional) Return all fields if Bool *True*.

**Returns** `packages.Page` object

**lock** (*id*)

Lock a package. Locking prevents the package from being modified or deleted until it is unlocked.

**Parameters** *id* – Package ID as an int.

**Returns** `packages.Package` object

**Return type** *packages.Package*

**testlist\_expanded** (*id*)

Get a list of all tests in a package, with any addons, modules or testlists expanded.

**Parameters** *id* – Package ID as an int.

**Return type** string list

**unlock** (*id*)

Unlock a package. Unlocking a locked package allows it to be modified or deleted once again.

**Parameters** *id* – Package ID as an int.

**Returns** `packages.Package` object

**Return type** *packages.Package*

## 2.7.2 Package

**class** `cdrouter.packages.Package (**kwargs)`  
Model for CDRouter Packages.

### Parameters

- **id** – (optional) Package ID as an int.
- **name** – (optional) Name as a string.
- **description** – (optional) Description as a string.
- **created** – (optional) Creation time as *DateTime*.
- **updated** – (optional) Last-updated time as *DateTime*.
- **locked** – (optional) Bool *True* if package is locked.
- **test\_count** – (optional) Test count as an int.
- **testlist** – (optional) Testlist as a string list.
- **extra\_cli\_args** – (optional) Extra CLI args as a string.
- **user\_id** – (optional) User ID as an int.
- **agent\_id** – (optional) Agent ID as an int.
- **config\_id** – (optional) Config ID as an int.
- **result\_id** – (optional) Result ID as an int (if a package snapshot).
- **device\_id** – (optional) Device ID as an int.
- **options** – (optional) `packages.Options` object
- **tags** – (optional) Tags as a string list.
- **use\_as\_testlist** – (optional) Bool *True* if package is used as a testlist.
- **note** – (optional) Note as a string.
- **schedule** – (optional) `packages.Schedule` object
- **interfaces** – (optional) `configs.Interfaces` list (if a package snapshot).

## 2.7.3 Options

**class** `cdrouter.packages.Options (**kwargs)`  
Model for CDRouter Package Options.

### Parameters

- **forever** – (optional) Bool *True* if package looped forever.
- **loop** – (optional) Loop count as an int.
- **repeat** – (optional) Repeat count as an int.
- **maxfail** – (optional) Max fail count as an int.
- **duration** – (optional) Max testing time duration as an int.
- **duration\_units** – (optional) Units for max testing time duration as string. Must be *seconds*, *minutes*, *hours* or *days*.

- **duration\_interrupt** – (optional) Bool *True* if max testing time duration elapsing should interrupt currently running test.
- **duration\_no\_error** – (optional) Bool *True* if max testing time duration elapsing should not be considered an error.
- **wait** – (optional) Wait between tests duration as an int.
- **pause** – (optional) Bool *True* if pausing between tests.
- **shuffle** – (optional) Bool *True* if testlist is shuffled.
- **seed** – (optional) Shuffle seed as an int.
- **retry** – (optional) Retry count as an int.
- **rdelay** – (optional) Retry delay as an int.

## 2.7.4 Schedule

**class** `cdrouter.packages.Schedule` (*\*\*kwargs*)  
Model for CDRouter Package Schedule.

### Parameters

- **enabled** – (optional) Bool *True* if schedule is enabled.
- **spec** – (optional) Cron spec schedule as a string.
- **options** – (optional) `results.Options` object

## 2.7.5 Page

**class** `cdrouter.packages.Page`  
Named tuple for a page of list response data.

### Parameters

- **data** – `packages.Package` list
- **links** – `cdrouter.Links` object

## 2.7.6 Analysis

**class** `cdrouter.packages.Analysis` (*\*\*kwargs*)  
Model for CDRouter Package Analysis.

### Parameters

- **total\_count** – (optional) Total count as an int.
- **run\_count** – (optional) Run count as an int.
- **skipped\_count** – (optional) Skipped test count as an int.
- **skipped\_tests** – (optional) Skipped tests as a string list.



## 2.8 Results

### 2.8.1 ResultsService

**class** `cdrouter.results.ResultsService` (*service*)

Service for accessing CDRouter Results.

**all\_stats** ()

Compute stats for all results.

**Returns** `results.AllStats` object

**Return type** *results.AllStats*

**bulk\_delete** (*ids=None, filter=None, type=None, all=False*)

Bulk delete a set of results.

**Parameters**

- **ids** – (optional) Int list of result IDs.
- **filter** – (optional) String list of filters.
- **type** – (optional) *union* or *inter* as string.
- **all** – (optional) Apply to all if bool *True*.

**bulk\_edit** (*\_fields, ids=None, filter=None, type=None, all=False*)

Bulk edit a set of results.

**Parameters**

- **\_fields** – `results.Result` object
- **ids** – (optional) Int list of result IDs.
- **filter** – (optional) String list of filters.
- **type** – (optional) *union* or *inter* as string.
- **all** – (optional) Apply to all if bool *True*.

**bulk\_export** (*ids, exclude\_captures=False*)

Bulk export a set of results.

**Parameters** **ids** – Int list of result IDs.

**Return type** tuple (*io.BytesIO*, *filename*)

**delete** (*id*)

Delete a result.

**Parameters** **id** – Result ID as an int.

**diff\_stats** (*ids*)

Compute diff stats for a set of results.

**Parameters** **id** – Result IDs as int list.

**Returns** `results.DiffStats` object

**Return type** *results.DiffStats*

**download\_logdir\_archive** (*id, format='zip', exclude\_captures=False*)

Download logdir archive in tgz or zip format.

**Parameters**

- **id** – Result ID as an int.
- **format** – (optional) Format to download, must be string *zip* or *tgz*.
- **exclude\_captures** – If bool *True*, don't include capture files

**Return type** tuple (*io.BytesIO*, 'filename')

**edit** (*resource*)

Edit a result.

**Parameters** **resource** – *results.Result* object

**Returns** *results.Result* object

**Return type** *results.Result*

**edit\_shares** (*id*, *user\_ids*)

Edit shares for a result.

**Parameters**

- **id** – Result ID as an int.
- **user\_ids** – User IDs as int list.

**Returns** *cdrouter.Share* list

**export** (*id*, *exclude\_captures=False*)

Export a result.

**Parameters**

- **id** – Result ID as an int.
- **exclude\_captures** – If bool *True*, don't export capture files

**Return type** tuple (*io.BytesIO*, 'filename')

**get** (*id*)

Get a result.

**Parameters** **id** – Result ID as an int.

**Returns** *results.Result* object

**Return type** *results.Result*

**get\_logdir\_file** (*id*, *filename*)

Download a logdir file.

**Parameters**

- **id** – Result ID as an int.
- **filename** – Logdir filename as string.

**Return type** tuple (*io.BytesIO*, 'filename')

**get\_shares** (*id*)

Get shares for a result.

**Parameters** **id** – Result ID as an int.

**Returns** *cdrouter.Share* list

**get\_test\_metric** (*id, tname, metric*)

Get a test graph metric. This method is only for getting “bandwidth” or “latency” test metrics.

This method is DEPRECATED since cdrouter.py v0.9.0, new code should use TestResultsService.get\_test\_metric instead.

**Parameters**

- **id** – Result ID as an int.
- **tname** – Test name as string.
- **metric** – Metric name as string.

**Returns** `metrics.GraphMetric` list

**Return type** `metrics.GraphMetric`

**get\_test\_metric\_csv** (*id, tname, metric*)

Get a test metric as CSV. This method is only for getting “bandwidth” or “latency” test metrics.

**Parameters**

- **id** – Result ID as an int.
- **tname** – Test name as string.
- **metric** – Metric name as string.

**Return type** string

**iter\_list** (*\*args, \*\*kwargs*)

Get a list of results. Whereas `list` fetches a single page of results according to its `limit` and `page` arguments, `iter_list` returns all results by internally making successive calls to `list`.

**Parameters**

- **args** – Arguments that `list` takes.
- **kwargs** – Optional arguments that `list` takes.

**Returns** `results.Result` list

**list** (*filter=None, type=None, sort=None, limit=None, page=None, detailed=None*)

Get a list of results, using summary representation by default (see `detailed` parameter).

**Parameters**

- **filter** – (optional) Filters to apply as a string list.
- **type** – (optional) *union* or *inter* as string.
- **sort** – (optional) Sort fields to apply as string list.
- **limit** – (optional) Limit returned list length.
- **page** – (optional) Page to return.
- **detailed** – (optional) Return all fields if Bool *True*.

**Returns** `results.Page` object

**list\_csv** (*filter=None, type=None, sort=None, limit=None, page=None*)

Get a list of results as CSV.

**Parameters**

- **filter** – (optional) Filters to apply as a string list.

- **type** – (optional) *union* or *inter* as string.
- **sort** – (optional) Sort fields to apply as string list.
- **limit** – (optional) Limit returned list length.
- **page** – (optional) Page to return.

**Return type** string

**list\_logdir** (*id*, *filter=None*, *sort=None*)

Get a list of logdir files.

**Parameters**

- **id** – Result ID as an int.
- **filter** – Filter to apply as string.
- **sort** – Sort field to apply as string.

**Returns** `results.LogDirFile` list

**list\_metrics** (*id*, *filter=None*, *type=None*, *sort=None*, *limit=None*, *page=None*, *detailed=None*)

Get a list of metrics, using summary representation by default (see `detailed` parameter).

**Parameters**

- **id** – Result ID as an int.
- **filter** – (optional) Filters to apply as a string list.
- **type** – (optional) *union* or *inter* as string.
- **sort** – (optional) Sort fields to apply as string list.
- **limit** – (optional) Limit returned list length.
- **page** – (optional) Page to return.
- **detailed** – (optional) Return all fields if Bool *True*.

**Returns** `metrics.Page` object

**Return type** `metrics.Page`

**lock** (*id*)

Lock a result. Locking prevents the result from being modified or deleted until it is unlocked.

**Parameters** **id** – Result ID as an int.

**Returns** `results.Result` object

**Return type** `results.Result`

**pause** (*id*, *when=None*)

Pause a running result.

**Parameters**

- **id** – Result ID as an int.
- **when** – Must be string *end-of-test* or *end-of-loop*.

**pause\_end\_of\_loop** (*id*)

Pause a running result at the end of the current loop.

**Parameters** **id** – Result ID as an int.

**pause\_end\_of\_test** (*id*)

Pause a running result at the end of the current test.

**Parameters** *id* – Result ID as an int.

**progress\_stats** (*id*)

Compute progress stats for a result.

**Parameters** *id* – Result ID as an int.

**Returns** `results.Progress` object

**Return type** *results.Progress*

**set\_stats** (*ids*)

Compute stats for a set of results.

**Parameters** *id* – Result IDs as int list.

**Returns** `results.SetStats` object

**Return type** *results.SetStats*

**single\_stats** (*id*)

Compute stats for a result.

**Parameters** *id* – Result ID as an int.

**Returns** `results.SingleStats` object

**Return type** *results.SingleStats*

**stop** (*id*, *when=None*)

Stop a running result.

**Parameters**

- *id* – Result ID as an int.
- *when* – Must be string *end-of-test* or *end-of-loop*.

**stop\_end\_of\_loop** (*id*)

Stop a running result at the end of the current loop.

**Parameters** *id* – Result ID as an int.

**stop\_end\_of\_test** (*id*)

Stop a running result at the end of the current test.

**Parameters** *id* – Result ID as an int.

**summary\_stats** (*id*)

Compute summary stats for a result.

**Parameters** *id* – Result ID as an int.

**Returns** `results.SummaryStats` object

**Return type** *results.SummaryStats*

**unlock** (*id*)

Unlock a result. Unlocking a locked result allows it to be modified or deleted once again.

**Parameters** *id* – Result ID as an int.

**Returns** `results.Result` object

**Return type** *results.Result*

**unpause** (*id*)

Unpause a running result.

**Parameters** *id* – Result ID as an int.

**updates** (*id*, *update\_id=None*)

Get updates of a running result via long-polling. If no updates are available, CDRouter waits up to 10 seconds before sending an empty response.

**Parameters**

- *id* – Result ID as an int.
- *update\_id* – (optional) Update ID as an int.

**Returns** `results.Update` object

**Return type** `results.Update`

## 2.8.2 Result

**class** `cdrouter.results.Result` (*\*\*kwargs*)

Model for CDRouter Results.

**Parameters**

- *id* – (optional) Result ID as an int.
- *created* – (optional) Creation time as *DateTime*.
- *updated* – (optional) Last-updated time as *DateTime*.
- *locked* – (optional) Bool *True* if result is locked.
- *result* – (optional) Result as a string.
- *active* – (optional) Bool *True* if status is ‘running’ or ‘paused’.
- *status* – (optional) Status as a string.
- *loops* – (optional) Loop count as an int.
- *tests* – (optional) Test count as an int.
- *passed* – (optional) Passed count as an int.
- *fail* – (optional) Failed count as an int.
- *alerts* – (optional) Alert count as an int.
- *duration* – (optional) Duration in seconds as an int.
- *size\_on\_disk* – (optional) Size on disk in bytes as an int.
- *starred* – (optional) Bool *True* if result is starred.
- *archived* – (optional) Bool *True* if result is archived.
- *result\_dir* – (optional) Filepath to result directory as a string.
- *agent\_name* – (optional) Agent name as a string.
- *package\_name* – (optional) Package name as a string.
- *device\_name* – (optional) Device name as a string.
- *config\_name* – (optional) Config name as a string.

- **package\_id** – (optional) Package ID as an int.
- **device\_id** – (optional) Device ID as an int.
- **config\_id** – (optional) Config ID as an int.
- **user\_id** – (optional) User ID as an int.
- **note** – (optional) Note as a string.
- **pause\_message** – (optional) Pause message as a string (if currently paused).
- **build\_info** – (optional) Build info as a string.
- **tags** – (optional) Tags as a string list.
- **testcases** – (optional) Testcases as a string list.
- **options** – (optional) `results.Options` object
- **features** – (optional) Dict of feature name strings to `results.Feature` objects.
- **interfaces** – (optional) `configs.Interfaces` list.

### 2.8.3 Page

**class** `cdrouter.results.Page`

Named tuple for a page of list response data.

#### Parameters

- **data** – `results.Result` list
- **links** – `cdrouter.Links` object

### 2.8.4 TestCount

**class** `cdrouter.results.TestCount` (*\*\*kwargs*)

Model for CDRouter Test Counts.

#### Parameters

- **name** – (optional) Name as a string.
- **count** – (optional) Count as an int.

### 2.8.5 TestDuration

**class** `cdrouter.results.TestDuration` (*\*\*kwargs*)

Model for CDRouter Test Durations.

#### Parameters

- **name** – (optional) Name as a string.
- **duration** – (optional) Duration as an int.

## 2.8.6 ResultBreakdown

**class** cdrouter.results.ResultBreakdown (\*\*kwargs)  
Model for CDRouter Result Breakdowns.

### Parameters

- **passed** – (optional) Pass count as an int.
- **failed** – (optional) Fail count as an int.
- **skipped** – (optional) Skipped count as an int.
- **alerted** – (optional) Alerted count as an int.

## 2.8.7 TimeBreakdown

**class** cdrouter.results.TimeBreakdown (\*\*kwargs)  
Model for CDRouter Time Breakdowns.

### Parameters

- **passed** – (optional) Pass duration as an int.
- **failed** – (optional) Fail duration as an int.

## 2.8.8 SetStats

**class** cdrouter.results.SetStats (\*\*kwargs)  
Model for CDRouter Result Set Stats.

### Parameters

- **frequent\_failures** – (optional) results.TestCount list
- **longest\_tests** – (optional) results.TestDuration list
- **result\_breakdown** – (optional) results.ResultBreakdown object
- **time\_breakdown** – (optional) results.TimeBreakdown object

## 2.8.9 TestResultSummary

**class** cdrouter.results.TestResultSummary (\*\*kwargs)  
Model for CDRouter TestResult summaries.

### Parameters

- **id** – (optional) Result ID as an int.
- **seq** – (optional) TestResult sequence ID as an int.
- **result** – (optional) Test result as string.
- **alerts** – (optional) Alert count as an int.
- **duration** – (optional) Test duration as int.
- **flagged** – (optional) *True* if test is flagged.
- **name** – (optional) Test name as string.



- **description** – (optional) Test description as string.

### 2.8.10 TestResultDiff

**class** cdrouter.results.**TestResultDiff** (\*\*kwargs)

Model for CDRouter TestResult diffs.

#### Parameters

- **name** – (optional) Test name as a string.
- **summaries** – (optional) results.TestResultSummary list

### 2.8.11 DiffStats

**class** cdrouter.results.**DiffStats** (\*\*kwargs)

Model for CDRouter Result Diff Stats.

**Parameters** **tests** – (optional) results.TestResultDiff list

### 2.8.12 TestResultBreakdown

**class** cdrouter.results.**TestResultBreakdown** (\*\*kwargs)

Model for CDRouter TestResult Breakdowns.

#### Parameters

- **failed\_at\_least\_once** – (optional) results.TestCount list
- **passed\_every\_time** – (optional) results.TestCount list

### 2.8.13 Progress

**class** cdrouter.results.**Progress** (\*\*kwargs)

Model for CDRouter Result Progress.

#### Parameters

- **finished** – (optional) Finished count as an int.
- **total** – (optional) Total count as an int.
- **progress** – (optional) Progress as an int.
- **unit** – (optional) Unit as a string.

### 2.8.14 SingleStats

**class** cdrouter.results.**SingleStats** (\*\*kwargs)

Model for CDRouter Single Results Stats.

#### Parameters

- **result\_breakdown** – (optional) results.ResultBreakdown object
- **progress** – (optional) results.Progress object

### 2.8.15 SummaryStats

**class** `cdrouter.results.SummaryStats` (*\*\*kwargs*)  
Model for CDRouter Summary Results Stats.

**Parameters**

- **result\_breakdown** – (optional) `results.ResultBreakdown` object
- **test\_summaries** – (optional) `testresults.TestResult` list

### 2.8.16 PackageCount

**class** `cdrouter.results.PackageCount` (*\*\*kwargs*)  
Model for CDRouter Package Counts.

**Parameters**

- **package\_name** – (optional) Package name as a string.
- **count** – (optional) Count as an int.

### 2.8.17 DeviceCount

**class** `cdrouter.results.DeviceCount` (*\*\*kwargs*)  
Model for CDRouter Device Counts.

**Parameters**

- **device\_name** – (optional) Device name as a string.
- **count** – (optional) Count as an int.

### 2.8.18 AllStats

**class** `cdrouter.results.AllStats` (*\*\*kwargs*)  
Model for CDRouter All Results Stats.

**Parameters**

- **frequent\_packages** – (optional) `results.PackageCount` list
- **package\_names** – (optional) `results.PackageCount` list
- **frequent\_devices** – (optional) `results.DeviceCount` list
- **device\_names** – (optional) `results.DeviceCount` list

### 2.8.19 LogDirFile

**class** `cdrouter.results.LogDirFile` (*\*\*kwargs*)  
Model for CDRouter Logdir Files.

**Parameters**

- **name** – (optional) Name as a string.
- **size** – (optional) Filesize as an int.

- **modified** – (optional) Last-updated time as a *DateTime*.

## 2.8.20 Options

**class** cdrouter.results.Options (\*\*kwargs)

Model for CDRouter Result Options.

### Parameters

- **tags** – (optional) Tags as string list.
- **skip\_tests** – (optional) Tests to skip as string list.
- **begin\_at** – (optional) Test name to begin testing at as string.
- **end\_at** – (optional) Test name to end testing at as string.
- **testvars** – (optional) Extra testvars to set as a `configs.Testvar` list.
- **extra\_cli\_args** – (optional) Extra *cdrouter-cli* arguments as string.

## 2.8.21 Feature

**class** cdrouter.results.Feature (\*\*kwargs)

Model for CDRouter Result Feature.

### Parameters

- **feature** – (optional) Feature as a string.
- **enabled** – (optional) *True* if feature is enabled.
- **reason** – (optional) Reason as a string

## 2.8.22 Update

**class** cdrouter.results.Update (\*\*kwargs)

Model for CDRouter Result Update.

### Parameters

- **id** – (optional) Update ID as an int.
- **timestamp** – (optional) System time as *DateTime*.
- **progress** – (optional) `results.Progress` object
- **running** – (optional) `testresults.TestResult` object
- **updates** – (optional) `results.Result`, `testresults.TestResult` and `alerts.Alert` list

## 2.8.23 Result

**class** cdrouter.results.Result (\*\*kwargs)

Model for CDRouter Results.

### Parameters

- **id** – (optional) Result ID as an int.

- **created** – (optional) Creation time as *DateTime*.
- **updated** – (optional) Last-updated time as *DateTime*.
- **locked** – (optional) Bool *True* if result is locked.
- **result** – (optional) Result as a string.
- **active** – (optional) Bool *True* if status is ‘running’ or ‘paused’.
- **status** – (optional) Status as a string.
- **loops** – (optional) Loop count as an int.
- **tests** – (optional) Test count as an int.
- **passed** – (optional) Passed count as an int.
- **fail** – (optional) Failed count as an int.
- **alerts** – (optional) Alert count as an int.
- **duration** – (optional) Duration in seconds as an int.
- **size\_on\_disk** – (optional) Size on disk in bytes as an int.
- **starred** – (optional) Bool *True* if result is starred.
- **archived** – (optional) Bool *True* if result is archived.
- **result\_dir** – (optional) Filepath to result directory as a string.
- **agent\_name** – (optional) Agent name as a string.
- **package\_name** – (optional) Package name as a string.
- **device\_name** – (optional) Device name as a string.
- **config\_name** – (optional) Config name as a string.
- **package\_id** – (optional) Package ID as an int.
- **device\_id** – (optional) Device ID as an int.
- **config\_id** – (optional) Config ID as an int.
- **user\_id** – (optional) User ID as an int.
- **note** – (optional) Note as a string.
- **pause\_message** – (optional) Pause message as a string (if currently paused).
- **build\_info** – (optional) Build info as a string.
- **tags** – (optional) Tags as a string list.
- **testcases** – (optional) Testcases as a string list.
- **options** – (optional) `results.Options` object
- **features** – (optional) Dict of feature name strings to `results.Feature` objects.
- **interfaces** – (optional) `configs.Interfaces` list.

## 2.9 Alerts

### 2.9.1 AlertsService

**class** `cdrouter.alerts.AlertsService` (*service*)

Service for accessing CDRouter Alerts.

**all\_stats** (*id*)

Compute alert stats for a single result.

**Parameters** *id* – Result ID as an int.

**Returns** `alerts.AllStats` object

**Return type** `alerts.AllStats`

**get** (*id*, *idx*)

Get an alert.

**Parameters**

- *id* – Result ID as an int.
- *idx* – Alert index as an int.

**Returns** `alerts.Alert` object

**Return type** `alerts.Alert`

**iter\_list** (*id*, *\*args*, *\*\*kwargs*)

Get a list of alerts. Whereas `list` fetches a single page of alerts according to its `limit` and `page` arguments, `iter_list` returns all alerts by internally making successive calls to `list`.

**Parameters**

- *id* – Result ID as an int.
- *args* – Arguments that `list` takes.
- *kwargs* – Optional arguments that `list` takes.

**Returns** `alerts.Alert` list

**list** (*id*, *filter=None*, *type=None*, *sort=None*, *limit=None*, *page=None*, *detailed=None*)

Get a list of alerts, using summary representation by default (see `detailed` parameter).

**Parameters**

- *id* – Result ID as an int.
- *filter* – (optional) Filters to apply as a string list.
- *type* – (optional) *union* or *inter* as string.
- *sort* – (optional) Sort fields to apply as string list.
- *limit* – (optional) Limit returned list length.
- *page* – (optional) Page to return.
- *detailed* – (optional) Return all fields if Bool *True*.

**Returns** `alerts.Page` object

## 2.9.2 Alert

**class** `cdrouter.alerts.Alert` (*\*\*kwargs*)  
Model for CDRouter Alerts.

### Parameters

- **id** – (optional) Result ID as an int.
- **idx** – (optional) Alert index as an int.
- **created** – (optional) Creation time as *DateTime*.
- **updated** – (optional) Last-updated time as *DateTime*.
- **seq** – (optional) TestResult sequence ID as an int.
- **loop** – (optional) Loop number as an int.
- **test\_name** – (optional) Test name as string.
- **test\_description** – (optional) Test description as string.
- **category** – (optional) Alert category as a string.
- **description** – (optional) Alert description as a string.
- **dest\_ip** – (optional) Alert destination IP as a string.
- **dest\_port** – (optional) Alert destination port as an int.
- **interface** – (optional) Alert incoming interface as a string.
- **payload** – (optional) Alert payload as a base64 string.
- **payload\_ascii** – (optional) Alert payload as an ASCII string.
- **payload\_hex** – (optional) Alert payload as a hex string.
- **proto** – (optional) Alert protocol as a string.
- **references** – (optional) Alert references as a string list.
- **rev** – (optional) Alert rule revision as an int.
- **rule** – (optional) Alert rule as a string.
- **rule\_set** – (optional) Alert rule set as a string.
- **severity** – (optional) Alert severity as an int.
- **sid** – (optional) Alert rule SID as an int.
- **signature** – (optional) Alert signature as a string.
- **src\_ip** – (optional) Alert source IP as a string.
- **src\_port** – (optional) Alert source port as an int.

## 2.9.3 Page

**class** `cdrouter.alerts.Page`  
Named tuple for a page of list response data.

### Parameters

- **data** – `alerts.Alert` list

- **links** – `cdrouter.Links` object

## 2.9.4 SeverityCount

**class** `cdrouter.alerts.SeverityCount` (*\*\*kwargs*)  
Model for CDRouter Severity Counts.

### Parameters

- **name** – (optional) Severity name as a string.
- **severity** – (optional) Severity as an int.
- **count** – (optional) Count as an int.

## 2.9.5 CategoryCount

**class** `cdrouter.alerts.CategoryCount` (*\*\*kwargs*)  
Model for CDRouter Category Counts.

### Parameters

- **category** – (optional) Category name as a string.
- **severity** – (optional) Severity as an int.
- **count** – (optional) Count as an int.

## 2.9.6 RuleSetCount

**class** `cdrouter.alerts.RuleSetCount` (*\*\*kwargs*)  
Model for CDRouter RuleSet Counts.

### Parameters

- **name** – (optional) RuleSet name as a string.
- **count** – (optional) Count as an int.

## 2.9.7 SignatureCount

**class** `cdrouter.alerts.SignatureCount` (*\*\*kwargs*)  
Model for CDRouter Signature Counts.

### Parameters

- **signature** – (optional) Signature name as a string.
- **severity** – (optional) Severity as an int.
- **count** – (optional) Count as an int.

## 2.9.8 TestCount

**class** `cdrouter.alerts.TestCount` (*\*\*kwargs*)  
Model for CDRouter Test Counts.

### Parameters

- **name** – (optional) Test name as a string.
- **count** – (optional) Count as an int.

## 2.9.9 AddrCount

**class** `cdrouter.alerts.AddrCount` (*\*\*kwargs*)  
Model for CDRouter Addr Counts.

### Parameters

- **addr** – (optional) Address as a string.
- **count** – (optional) Count as an int.

## 2.9.10 AllStats

**class** `cdrouter.alerts.AllStats` (*\*\*kwargs*)  
Model for CDRouter All Alerts Stats.

### Parameters

- **severities** – (optional) Dict of ints to `alerts.SeverityCount`
- **categories** – (optional) `alerts.CategoryCount` list
- **rule\_sets** – (optional) `alerts.RuleSetCount` list
- **signatures** – (optional) `alerts.SignatureCount` list
- **tests** – (optional) `alerts.TestCount` list
- **frequent\_sources** – (optional) `alerts.AddrCount` list
- **frequent\_destinations** – (optional) `alerts.AddrCount` list

## 2.10 TestResults

### 2.10.1 TestResultsService

**class** `cdrouter.testresults.TestResultsService` (*service*)  
Service for accessing CDRouter TestResults.

**edit** (*resource*)  
Edit a test result.

**Parameters** **resource** – `testresults.TestResult` object

**Returns** `testresults.TestResult` object

**Return type** *testresults.TestResult*



**get** (*id*, *seq*)

Get a test result.

**Parameters**

- **id** – Result ID as an int.
- **seq** – TestResult sequence ID as an int.

**Returns** `testresults.TestResult` object

**Return type** `testresults.TestResult`

**get\_log\_plaintext** (*id*, *seq*)

Get a test result’s log as plaintext.

**Parameters**

- **id** – Result ID as an int.
- **seq** – TestResult sequence ID as an int.

**Return type** string

**get\_test\_metric** (*id*, *seq*, *metric*)

Get a bandwidth, latency, client\_bandwidth or client\_latency test metric. This method is only for getting “bandwidth”, “latency”, “client\_bandwidth” or “client\_lantecy” test metrics.

**Parameters**

- **id** – Result ID as an int.
- **seq** – TestResult sequence ID as an int.
- **metric** – Metric name as string, must be “bandwidth”, “latency”, “client\_bandwidth” or “client\_latency”

**Returns** `metrics.Bandwidth` list, `metrics.Latency` list, `metrics.ClientBandwidth` list or `metrics.ClientLatency` list

**Return type** Union[`metrics.Bandwidth`, `metrics.Latency`, `metrics.ClientBandwidth`, `metrics.ClientLatency`]

**get\_test\_metric\_csv** (*id*, *seq*, *metric*)

Get a test metric as CSV. This methods support all test metrics.

**Parameters**

- **id** – Result ID as an int.
- **seq** – TestResult sequence ID as an int.
- **id** – Metric name as string.

**Return type** string

**iter\_list** (*id*, *\*args*, *\*\*kwargs*)

Get a list of test results. Whereas `list` fetches a single page of test results according to its `limit` and `page` arguments, `iter_list` returns all test results by internally making successive calls to `list`.

**Parameters**

- **id** – Result ID as an int.
- **args** – Arguments that `list` takes.
- **kwargs** – Optional arguments that `list` takes.

**Returns** `testresults.TestResult` list

**iter\_list\_log** (*id*, *seq*, \**args*, \*\**kwargs*)

Get a test result's log. Whereas `list_log` fetches a single range of log lines according to its `limit` and `offset` arguments, `iter_list_log` returns all log lines by internally making successive calls to `list_log`.

**Parameters**

- **id** – Result ID as an int.
- **seq** – TestResult sequence ID as an int.
- **args** – Arguments that `list_log` takes.
- **kwargs** – Optional arguments that `list_log` takes.

**Returns** `testresults.Line` list

**list** (*id*, *filter*=None, *type*=None, *sort*=None, *limit*=None, *page*=None, *detailed*=None)

Get a list of test results, using summary representation by default (see `detailed` parameter).

**Parameters**

- **id** – Result ID as an int.
- **filter** – (optional) Filters to apply as a string list.
- **type** – (optional) *union* or *inter* as string.
- **sort** – (optional) Sort fields to apply as string list.
- **limit** – (optional) Limit returned list length.
- **page** – (optional) Page to return.
- **detailed** – (optional) Return all fields if Bool *True*.

**Returns** `testresults.Page` object

**list\_csv** (*id*, *filter*=None, *type*=None, *sort*=None, *limit*=None, *page*=None)

Get a list of test results as CSV.

**Parameters**

- **id** – Result ID as an int.
- **filter** – (optional) Filters to apply as a string list.
- **type** – (optional) *union* or *inter* as string.
- **sort** – (optional) Sort fields to apply as string list.
- **limit** – (optional) Limit returned list length.
- **page** – (optional) Page to return.

**Return type** string

**list\_log** (*id*, *seq*, *offset*=None, *limit*=None, *filter*=None, *packets*=None, *timestamp\_format*=None)

Get a test result's log.

**Parameters**

- **id** – Result ID as an int.
- **seq** – TestResult sequence ID as an int.
- **offset** – (optional) Offset within logfile to get.

- **limit** – (optional) Limit returned list length.
- **filter** – (optional) Filters to apply as a string list.
- **packets** – (optional) Set to bool *False* to omit packet logs.
- **timestamp\_format** – (optional) Timestamp format to use, must be string *long* or *short*.

**Returns** `testresults.Log` object

**Return type** `testresults.Log`

**list\_metrics** (*id*, *seq*, *filter=None*, *type=None*, *sort=None*, *limit=None*, *page=None*, *detailed=None*)

Get a list of metrics, using summary representation by default (see *detailed* parameter).

**Parameters**

- **id** – Result ID as an int.
- **seq** – TestResult sequence ID as an int.
- **filter** – (optional) Filters to apply as a string list.
- **type** – (optional) *union* or *inter* as string.
- **sort** – (optional) Sort fields to apply as string list.
- **limit** – (optional) Limit returned list length.
- **page** – (optional) Page to return.
- **detailed** – (optional) Return all fields if Bool *True*.

**Returns** `metrics.Page` object

**Return type** `metrics.Page`

## 2.10.2 TestResult

**class** `cdrouter.testresults.TestResult` (*\*\*kwargs*)

Model for CDRouter TestResults.

**Parameters**

- **id** – (optional) Result ID as an int.
- **seq** – (optional) TestResult sequence ID as an int.
- **loop** – (optional) Loop number as an int.
- **active** – (optional) Bool *True* if result is ‘running’ or ‘waiting’.
- **result** – (optional) Test result as string.
- **alerts** – (optional) Alerts count as int.
- **retries** – (optional) Retry count as int.
- **started** – (optional) Test start time as *DateTime*.
- **duration** – (optional) Test duration as int.
- **flagged** – (optional) *True* if test is flagged.
- **name** – (optional) Test name as string.

- **description** – (optional) Test description as string.
- **skip\_name** – (optional) Skip name for TestResult as string.
- **skip\_reason** – (optional) Skip reason for TestResult as string.
- **log** – (optional) Logfile path for TestResult as string.
- **keylog** – (optional) Keylog path for TestResult as string.
- **note** – (optional) Note for TestResult as string.

### 2.10.3 Page

**class** `cdrouter.testresults.Page`

Named tuple for a page of list response data.

#### Parameters

- **data** – `testresults.TestResult` list
- **links** – `cdrouter.Links` object

### 2.10.4 Summary

**class** `cdrouter.testresults.Summary` (*\*\*kwargs*)

Model for CDRouter Log Section Summaries.

#### Parameters

- **errors** – (optional) Error log count as int.
- **fails** – (optional) Fail log count as int.
- **passes** – (optional) Pass log count as int.
- **warnings** – (optional) Warning log count as int.
- **alerts** – (optional) Alert log count as int.

### 2.10.5 Line

**class** `cdrouter.testresults.Line` (*\*\*kwargs*)

Model for CDRouter Log Lines.

#### Parameters

- **raw** – (optional) Raw log text as string.
- **line** – (optional) Line number as int.
- **header** – (optional) *True* if line is a header.
- **section** – (optional) *True* if line is a section.
- **prefix** – (optional) Log prefix as string.
- **name** – (optional) Log stack name as string.
- **timestamp** – (optional) Log timestamp as string.
- **timestamp\_display** – (optional) Log display timestamp as string.

- **message** – (optional) Log message as string.
- **interface** – (optional) Log interface as string (if packet log).
- **packet** – (optional) Log frame number as an int (if packet log).
- **src** – (optional) Log source address as string (if packet log).
- **dst** – (optional) Log destination address as string (if packet log).
- **proto** – (optional) Log protocol name as string (if packet log).
- **info** – (optional) Log protocol summary as string (if packet log).
- **alert\_interface** – (optional) Log alert interface as string (if alert log).
- **alert\_index** – (optional) Log alert index as an int (if alert log).
- **alert\_src** – (optional) Log alert source address as string (if alert log).
- **alert\_dst** – (optional) Log alert destination address as string (if alert log).
- **alert\_proto** – (optional) Log alert protocol name as string (if alert log).
- **alert\_src\_port** – (optional) Log alert source port as int (if alert log).
- **alert\_dst\_port** – (optional) Log alert destination port as int (if alert log).
- **alert\_signature** – (optional) Log alert signature as string (if alert log).
- **alert\_severity** – (optional) Log alert severity as int (if alert log).
- **alert\_severity\_display** – (optional) Log alert display severity as string (if alert log).
- **alert\_sid** – (optional) Log alert SID as int (if alert log).
- **alert\_rev** – (optional) Log alert revision as int (if alert log).
- **summary** – (optional) `testresults.Summary` object (if section log)

## 2.10.6 Log

**class** `cdrouter.testresults.Log` (*\*\*kwargs*)

Model for CDRouter Log.

### Parameters

- **offset** – (optional) Zero-based offset in logfile as int.
- **limit** – (optional) Limit as int.
- **lines** – (optional) `testresults.Line` list
- **total** – (optional) Total line count as int.
- **more** – (optional) Bool *True* if more lines are available.

## 2.11 Annotations

### 2.11.1 AnnotationsService

**class** `cdrouter.annotations.AnnotationsService` (*service*)

Service for accessing CDRouter Annotations.

**create** (*id, seq, resource*)

Create an annotation.

**Parameters**

- **id** – Result ID as an int.
- **seq** – TestResult sequence ID as an int.
- **resource** – `annotations.Annotation` object

**Returns** `annotations.Annotation` object

**Return type** `annotations.Annotation`

**create\_or\_edit** (*id, seq, resource*)

Create or edit an annotation.

**Parameters**

- **id** – Result ID as an int.
- **seq** – TestResult sequence ID as an int.
- **resource** – `annotations.Annotation` object

**Returns** `annotations.Annotation` object

**Return type** `annotations.Annotation`

**delete** (*id, seq, line*)

Delete an annotation.

**Parameters**

- **id** – Result ID as an int.
- **seq** – TestResult sequence ID as an int.
- **line** – Line number in TestResult's logfile as an int.

**edit** (*id, seq, resource*)

Edit an annotation.

**Parameters**

- **id** – Result ID as an int.
- **seq** – TestResult sequence ID as an int.
- **resource** – `annotations.Annotation` object

**Returns** `annotations.Annotation` object

**Return type** `annotations.Annotation`

**get** (*id, seq, line*)

Get an annotation.

**Parameters**

- **id** – Result ID as an int.
- **seq** – TestResult sequence ID as an int.
- **line** – Line number in TestResult's logfile as an int.

**Returns** `annotations.Annotation` object

**Return type** `annotations.Annotation`

**list** (*id, seq, detailed=None*)

Get a list of annotations, using summary representation by default (see *detailed* parameter).

**Parameters**

- **id** – Result ID as an int.
- **seq** – TestResult sequence ID as an int.
- **detailed** – (optional) Return all fields if Bool *True*.

**Returns** `annotations.Annotation` list

## 2.11.2 Annotation

**class** `cdrouter.annotations.Annotation` (*\*\*kwargs*)

Model for CDRouter Annotations.

**Parameters**

- **id** – (optional) Result ID as an int.
- **seq** – (optional) TestResult sequence ID as an int.
- **line** – (optional) Line number in TestResult’s logfile as an int.
- **comment** – (optional) Comment text as string.

## 2.12 Metrics

### 2.12.1 Bandwidth

**class** `cdrouter.metrics.Bandwidth` (*\*\*kwargs*)

Model for CDRouter Bandwidth Metrics.

**Parameters**

- **log\_file** – (optional) Filepath to logfile as a string.
- **timestamp** – (optional) Timestamp for metric as a *DateTime*.
- **metric** – (optional) Metric name as a string.
- **bandwidth** – (optional) Bandwidth value as a float.
- **bandwidth\_units** – (optional) Bandwidth value units as a string.
- **result** – (optional) Metric result as a string.
- **client\_interface** – (optional) Client interface as a string.
- **server\_interface** – (optional) Server interface as a string.
- **streams** – (optional) Stream count as an int.
- **protocol** – (optional) Protocol as a string.
- **direction** – (optional) Direction as a string.
- **loss\_percentage** – (optional) Loss percentage value as a float.
- **loss\_percentage\_units** – (optional) Loss percentage units as a string.
- **client\_device** – (optional) Client device as a string.

- **server\_device** – (optional) Server device as a string.

### 2.12.2 ClientBandwidth

**class** cdrouter.metrics.**ClientBandwidth** (\*\*kwargs)

Model for CDRouter Client Bandwidth Metrics.

#### Parameters

- **timestamp** – (optional) Timestamp for metric as a *DateTime*.
- **num\_rates** – (optional) Size of metric bandwidth rates list as an int.
- **rate** – (optional) Metric bandwidth rates as a float list.

### 2.12.3 ClientLatency

**class** cdrouter.metrics.**ClientLatency** (\*\*kwargs)

Model for CDRouter Client Latency Metrics.

#### Parameters

- **timestamp** – (optional) Timestamp for metric as a *DateTime*.
- **num\_rates** – (optional) Size of metric latency rates list as an int.
- **rate** – (optional) Metric latency rates as an int list.

### 2.12.4 GraphMetric

**class** cdrouter.metrics.**GraphMetric** (\*\*kwargs)

Model for CDRouter Graph Metrics.

#### Parameters

- **log\_file** – (optional) Filepath to logfile as a string.
- **timestamp** – (optional) Timestamp for metric as a *DateTime*.
- **metric** – (optional) Metric name as a string.
- **value** – (optional) First metric value as a float.
- **units** – (optional) First metric units as a string.
- **result** – (optional) Metric result as a string.
- **interface\_1** – (optional) First interface as a string.
- **interface\_2** – (optional) Second interface as a string.
- **streams** – (optional) Stream count as an int.
- **protocol** – (optional) Protocol as a string.
- **direction** – (optional) Direction as a string.
- **value\_2** – (optional) Second metric value as a float.
- **units\_2** – (optional) Second metric units as a string.
- **device\_1** – (optional) First device as a string.



- **device\_2** – (optional) Second device as a string.

### 2.12.5 Latency

**class** `cdrouter.metrics.Latency` (*\*\*kwargs*)

Model for CDRouter Latency Metrics.

#### Parameters

- **log\_file** – (optional) Filepath to logfile as a string.
- **timestamp** – (optional) Timestamp for metric as a *DateTime*.
- **metric** – (optional) Metric name as a string.
- **total\_latency** – (optional) Total latency value as an int.
- **total\_latency\_units** – (optional) Total latency units as a string.
- **result** – (optional) Metric result as a string.
- **interface** – (optional) Interface as a string.
- **download\_latency** – (optional) Download latency as an int.
- **download\_latency\_units** – (optional) Download latency units as a string.
- **upload\_latency** – (optional) Upload latency as an int.
- **upload\_latency\_units** – (optional) Upload latency units as a string.

### 2.12.6 Metric

**class** `cdrouter.metrics.Metric` (*\*\*kwargs*)

Model for CDRouter Metrics.

#### Parameters

- **id** – (optional) Result ID as an int.
- **seq** – (optional) TestResult sequence ID as an int.
- **created** – (optional) Creation time as *DateTime*.
- **updated** – (optional) Last-updated time as *DateTime*.
- **test\_name** – (optional) Test name as a string.
- **metric** – (optional) Metric name as a string.
- **filename** – (optional) Filename as a string.

### 2.12.7 Page

**class** `cdrouter.metrics.Page`

Named tuple for a page of list response data.

#### Parameters

- **data** – `metrics.Metric` list
- **links** – `cdrouter.Links` object

## 2.13 Captures

### 2.13.1 CapturesService

**class** `cdrouter.captures.CapturesService` (*service*)

Service for accessing CDRouter Captures.

**download** (*id, seq, intf, inline=False*)

Download a capture as a PCAP file.

**Parameters**

- **id** – Result ID as an int.
- **seq** – TestResult sequence ID as an int.
- **intf** – Interface name as string.
- **inline** – (optional) Use inline version of capture file.

**Return type** tuple (*io.BytesIO*, *'filename'*)

**get** (*id, seq, intf*)

Get a capture.

**Parameters**

- **id** – Result ID as an int.
- **seq** – TestResult sequence ID as an int.
- **intf** – Interface name as string.

**Returns** `captures.Capture` object

**Return type** *captures.Capture*

**list** (*id, seq, detailed=None*)

Get a list of captures, using summary representation by default (see `detailed` parameter).

**Parameters**

- **id** – Result ID as an int.
- **seq** – TestResult sequence ID as an int.
- **detailed** – (optional) Return all fields if Bool *True*.

**Returns** `captures.Capture` list

**send\_to\_cloudshark** (*id, seq, intf, inline=False*)

Send a capture to a CloudShark Appliance. Both `cloudshark_appliance_url` and `cloudshark_appliance_token` must be properly configured via system preferences.

**Parameters**

- **id** – Result ID as an int.
- **seq** – TestResult sequence ID as an int.
- **intf** – Interface name as string.
- **inline** – (optional) Use inline version of capture file.

**Returns** `captures.CloudShark` object

**Return type** *captures.CloudShark*

## 2.13.2 Capture

**class** `cdrouter.captures.Capture` (*\*\*kwargs*)  
Model for CDRouter Captures.

### Parameters

- **id** – (optional) Result ID as an int.
- **seq** – (optional) TestResult sequence ID as an int.
- **type** – (optional) Capture type as string.
- **interface** – (optional) Interface name as string.
- **filename** – (optional) Path to capture file as string.

## 2.13.3 CloudShark

**class** `cdrouter.captures.CloudShark` (*\*\*kwargs*)  
Model for CDRouter CloudShark uploads.

**Parameters** **url** – (optional) CloudShark URL as a string.

## 2.14 Highlights

### 2.14.1 HighlightsService

**class** `cdrouter.highlights.HighlightsService` (*service*)  
Service for accessing CDRouter Highlights.

**create** (*id, seq, resource*)  
Create a highlight.

### Parameters

- **id** – Result ID as an int.
- **seq** – TestResult sequence ID as an int.
- **resource** – `highlights.Highlight` object

**Returns** `highlights.Highlight` object

**Return type** *highlights.Highlight*

**create\_or\_edit** (*id, seq, resource*)  
Create or edit a highlight.

### Parameters

- **id** – Result ID as an int.
- **seq** – TestResult sequence ID as an int.
- **resource** – `highlights.Highlight` object

**Returns** `highlights.Highlight` object

**Return type** *highlights.Highlight*

**delete** (*id, seq, line*)  
Delete a highlight.

**Parameters**

- **id** – Result ID as an int.
- **seq** – TestResult sequence ID as an int.
- **line** – Line number in TestResult’s logfile as an int.

**edit** (*id, seq, resource*)  
Edit a highlight.

**Parameters**

- **id** – Result ID as an int.
- **seq** – TestResult sequence ID as an int.
- **resource** – `highlights.Highlight` object

**Returns** `highlights.Highlight` object

**Return type** *highlights.Highlight*

**get** (*id, seq, line*)  
Get a highlight.

**Parameters**

- **id** – Result ID as an int.
- **seq** – TestResult sequence ID as an int.
- **line** – Line number in TestResult’s logfile as an int.

**Returns** `highlights.Highlight` object

**list** (*id, seq, detailed=None*)  
Get a list of highlights, using summary representation by default (see `detailed` parameter).

**Parameters**

- **id** – Result ID as an int.
- **seq** – TestResult sequence ID as an int.
- **detailed** – (optional) Return all fields if Bool *True*.

**Returns** `highlights.Highlight` list

## 2.14.2 Highlight

**class** `cdrouter.highlights.Highlight` (*\*\*kwargs*)  
Model for CDRouter Highlights.

**Parameters**

- **id** – (optional) Result ID as an int.
- **seq** – (optional) TestResult sequence ID as an int.
- **line** – (optional) Line number in TestResult’s logfile as an int.
- **color** – (optional) Highlight color as string.

## 2.15 Imports

### 2.15.1 ImportsService

**class** `cdrouter.imports.ImportsService` (*service*)

Service for accessing CDRouter Imports.

**commit** (*id*, *impreq*)

Commit a staged import.

**Parameters**

- **id** – Staged import ID as an int.
- **impreq** – `imports.Request` object

**Returns** `imports.Request` object

**Return type** *imports.Request*

**delete** (*id*)

Delete a staged import.

**Parameters** **id** – Staged import ID as an int.

**get** (*id*)

Get a staged import.

**Parameters** **id** – Staged import ID as an int.

**Returns** `imports.Import` object

**Return type** *imports.Import*

**get\_commit\_request** (*id*)

Get a commit request for a staged import.

**Parameters** **id** – Staged import ID as an int.

**Returns** `imports.Request` object

**Return type** *imports.Request*

**list** ()

Get a list of staged (in-progress) imports.

**Returns** `imports.Import` list

**stage\_import\_from\_file** (*fd*, *filename*='upload.gz')

Stage an import from a file upload.

**Parameters**

- **fd** – File-like object to upload.
- **filename** – (optional) Filename to use for import as string.

**Returns** `imports.Import` object

**stage\_import\_from\_filesystem** (*filepath*)

Stage an import from a filesystem path.

**Parameters** **filepath** – Local filesystem path as string.

**Returns** `imports.Import` object

**stage\_import\_from\_url** (*url*, *token=None*, *username=None*, *password=None*, *insecure=False*)  
Stage an import from a URL to another CDRouter system.

**Parameters**

- **url** – URL to import as string.
- **token** – (optional) API token to use as string (may be required if importing from a CDRouter 10+ system).
- **username** – (optional) API username to use as string (may be required if importing from a CDRouter 10+ system).
- **password** – (optional) API password to use as string (may be required if importing from a CDRouter 10+ system).
- **insecure** – (optional) Allow insecure HTTPS connections if bool *True*.

**Returns** `imports.Import` object

## 2.15.2 Import

**class** `cdrouter.imports.Import` (*\*\*kwargs*)  
Model for CDRouter Staged Imports.

**Parameters**

- **id** – (optional) Staged import ID as an int.
- **user\_id** – (optional) User ID as an int.
- **created** – (optional) Creation time as *DateTime*.
- **updated** – (optional) Last-updated time as *DateTime*.
- **archive** – (optional) Path to archive as string.
- **path** – (optional) Local filepath as string.
- **url** – (optional) URL to fetch as string.
- **insecure** – (optional) Allow insecure HTTPS connections if bool *True*.
- **size** – (optional) Size of import as int.

## 2.15.3 Response

**class** `cdrouter.imports.Response` (*\*\*kwargs*)  
Model for CDRouter Import Responses.

**Parameters**

- **imported** – (optional) Bool *True* if resource imported successfully.
- **id** – (optional) Resource ID as an int.
- **name** – (optional) Resource name as string.
- **message** – (optional) Response message as string.

## 2.15.4 Resource

**class** `cdrouter.imports.Resource` (*\*\*kwargs*)  
Model for CDRouter Import Resources.

### Parameters

- **name** – (optional) Set to string to rename resource, leave empty to keep original
- **should\_import** – (optional) Bool *True* if resource should be imported.
- **existing\_id** – (optional) Contains ID as an int of existing resource which will be over-written if *should\_import* is *True*.
- **response** – (optional) `imports.Response` object

## 2.15.5 Request

**class** `cdrouter.imports.Request` (*\*\*kwargs*)  
Model for CDRouter Import Requests.

### Parameters

- **replace\_existing** – (optional) Bool *True* if existing resources should be overwritten.
- **configs** – (optional) Dict of strings to `imports.Resource` objects.
- **devices** – (optional) Dict of strings to `imports.Resource` objects.
- **packages** – (optional) Dict of strings to `imports.Resource` objects.
- **results** – (optional) Dict of strings to `imports.Resource` objects.
- **tags** – (optional) Tags to add to imported resources as string list.

## 2.16 Exports

### 2.16.1 ExportsService

**class** `cdrouter.exports.ExportsService` (*service*)  
Service for accessing CDRouter Exports.

**bulk\_export** (*config\_ids=None, device\_ids=None, package\_ids=None, result\_ids=None, exclude\_captures=False*)  
Bulk export a set of configs, devices, packages and results.

### Parameters

- **config\_ids** – (optional) Int list of config IDs.
- **device\_ids** – (optional) Int list of device IDs.
- **package\_ids** – (optional) Int list of package IDs.
- **result\_ids** – (optional) Int list of result IDs.
- **exclude\_captures** – (optional) Exclude capture files if bool *True*.

**Return type** tuple (*io.BytesIO, 'filename'*)

## 2.17 History

### 2.17.1 HistoryService

**class** `cdrouter.history.HistoryService(service)`

Service for accessing CDRouter History.

**iter\_list** (\*args, \*\*kwargs)

Get a list of history entries. Whereas `list` fetches a single page of history entries according to its `limit` and `page` arguments, `iter_list` returns all history entries by internally making successive calls to `list`.

**Parameters**

- **args** – Arguments that `list` takes.
- **kwargs** – Optional arguments that `list` takes.

**Returns** `historys.History` list

**list** (filter=None, type=None, sort=None, limit=None, page=None, detailed=None)

Get a list of history entries, using summary representation by default (see `detailed` parameter).

**Parameters**

- **filter** – (optional) Filters to apply as a string list.
- **type** – (optional) *union* or *inter* as string.
- **sort** – (optional) Sort fields to apply as string list.
- **limit** – (optional) Limit returned list length.
- **page** – (optional) Page to return.
- **detailed** – (optional) Return all fields if Bool *True*.

**Returns** `history.Page` object

### 2.17.2 History

**class** `cdrouter.history.History(**kwargs)`

Model for CDRouter History entries.

**Parameters**

- **user\_id** – (optional) User ID as an int.
- **created** – (optional) Entry creation time as *DateTime*.
- **resource** – (optional) Resource type as string.
- **id** – (optional) Resource ID as an int.
- **name** – (optional) Resource name as string.
- **action** – (optional) Action name as string.
- **description** – (optional) Resource description as string.



### 2.17.3 Page

**class** `cdrouter.history.Page`

Named tuple for a page of list response data.

**Parameters**

- **data** – `history.History` list
- **links** – `cdrouter.Links` object

## 2.18 System

### 2.18.1 SystemService

**class** `cdrouter.system.SystemService` (*service*)

Service for accessing CDRouter System.

**check\_for\_lounge\_upgrade** (*email*)

Check the CDRouter Support Lounge for eligible upgrades using your Support Lounge email.

**Parameters** **email** – CDRouter Support Lounge email as a string.

**Returns** `system.Release` object

**Return type** *system.Release*

**diagnostics** ()

Get system diagnostics from `cdrouter-diag` output.

**Return type** tuple (*io.BytesIO*, 'filename')

**edit\_preferences** (*resource*)

Edit preferences in `/usr/cdrouter-data/etc/config.yml`.

**Parameters** **resource** – `system.Preferences` object

**Returns** `system.Preferences` object

**Return type** *system.Preferences*

**get\_preferences** ()

Get preferences from `/usr/cdrouter-data/etc/config.yml`.

**Returns** `system.Preferences` object

**Return type** *system.Preferences*

**hostname** ()

Get system hostname.

**Return type** string

**in\_use\_interfaces** ()

Get system interfaces, with flags to determine which are in use.

**Returns** `system.InUseInterface` list

**info** ()

Get system info from `cdrouter-cli -info` output.

**Return type** string

**interfaces** (*addresses=False*)

Get system interfaces.

**Parameters** **addresses** – (optional) If bool *True*, include interface addresses.

**Returns** `system.Interface` list

**latest\_lounge\_release** ()

Get the latest release of CDRouter from the CDRouter Support Lounge.

**Returns** `system.ReleaseLatest` object

**Return type** *system.ReleaseLatest*

**lounge\_update\_license** ()

Download & install a license for your CDRouter system from the CDRouter Support Lounge.

**Returns** `system.Upgrade` object

**Return type** *system.Upgrade*

**lounge\_upgrade** (*email, nonce, filename='cdrouter.rpm'*)

Download & install an upgrade from the CDRouter Support Lounge using your Support Lounge email and upgrade nonce. Please note that any running tests will be stopped.

**Parameters**

- **email** – CDRouter Support Lounge email as a string.
- **nonce** – Upgrade nonce from `system.Release`.
- **filename** – Upgrade filename from `system.Release`.

**Returns** `system.Upgrade` object

**Return type** *system.Upgrade*

**manual\_update\_license** (*fd, filename='cdrouter.lic'*)

Update the license on your CDRouter system manually by uploading a `.lic` license from the CDRouter Support Lounge.

**Parameters**

- **fd** – File-like object to upload.
- **filename** – (optional) Filename to use for license as string.

**manual\_upgrade** (*fd, filename='cdrouter.rpm'*)

Upgrade CDRouter manually by uploading an `.rpm` installer from the CDRouter Support Lounge. Please note that any running tests will be stopped.

**Parameters**

- **fd** – File-like object to upload.
- **filename** – (optional) Filename to use for installer as string.

**Returns** `system.Upgrade` object

**Return type** *system.Upgrade*

**poweroff** ()

Poweroff the NTA1000. Please note that any running tests will be stopped.

**reboot** ()

Reboot the NTA1000. Please note that any running tests will be stopped.

**restart()**

Restart the CDRouter Web UI. Please note that any running tests will be stopped.

**shutdown()**

Shutdown the CDRouter Web UI. Please note that any running tests will be stopped.

**space()**

Get system disk space usage.

**Returns** `system.Space` object

**Return type** `system.Space`

**time()**

Get system time.

**Return type** string

## 2.18.2 Version

**class** `cdrouter.system.Version(**kwargs)`

Model for CDRouter Release Versions.

**Parameters**

- **raw** – (optional) Raw version as string.
- **major** – (optional) Major version as int.
- **minor** – (optional) Minor version as int.
- **build** – (optional) Build version as int.

## 2.18.3 ReleaseLatest

**class** `cdrouter.system.ReleaseLatest(**kwargs)`

Model for CDRouter Latest Releases.

**Parameters**

- **latest** – (optional) `system.Version` object.
- **current** – (optional) `system.Version` object.
- **newer** – (optional) Bool *True* if newer release available.

## 2.18.4 Testsuite

**class** `cdrouter.system.Testsuite(**kwargs)`

Model for CDRouter Testsuite names.

**Parameters**

- **shortname** – (optional) Brief testsuite name as string.
- **name** – (optional) Full testsuite name as string.

### 2.18.5 Release

**class** cdrouter.system.**Release** (\*\*kwargs)  
Model for CDRouter Releases.

#### Parameters

- **build\_date** – (optional) Build date as string.
- **filename** – (optional) Installer filename as string.
- **version** – (optional) `system.Version` object
- **testsuite** – (optional) `system.Testsuite` object
- **nonce** – (optional) Upgrade nonce as string.

### 2.18.6 Upgrade

**class** cdrouter.system.**Upgrade** (\*\*kwargs)  
Model for CDRouter Upgrades.

#### Parameters

- **success** – (optional) Bool *True* if successful.
- **installer\_path** – (optional) Installer filename as string.
- **output** – (optional) Output as string.
- **error** – (optional) Error output as string.

### 2.18.7 InterfaceFlags

**class** cdrouter.system.**InterfaceFlags** (\*\*kwargs)  
Model for CDRouter Interface Flags.

#### Parameters

- **up** – (optional) Bool *True* if interface is up.
- **broadcast** – (optional) Bool *True* if interface is broadcasting.
- **loopback** – (optional) Bool *True* if interface is a loopback interface.
- **point\_to\_point** – (optional) Bool *True* if interface is a point-to-point interface.
- **multicast** – (optional) Bool *True* if interface is multicast.

### 2.18.8 InterfaceAddr

**class** cdrouter.system.**InterfaceAddr** (\*\*kwargs)  
Model for CDRouter Interface Addresses.

#### Parameters

- **network** – (optional) Interface network as a string.
- **address** – (optional) Interface address as a string.

### 2.18.9 Interface

**class** cdrouter.system.**Interface** (\*\*kwargs)  
Model for CDRouter Interfaces.

#### Parameters

- **index** – (optional) Interface index as an int.
- **mtu** – (optional) Interface MTU as an int.
- **name** – (optional) Interface name as a string.
- **hardware\_addr** – (optional) Interface hardware address as a string.
- **flags** – (optional) `system.InterfaceFlags` object
- **addresses** – (optional) `system.InterfaceAddr` list
- **multicast\_addresses** – (optional) `system.InterfaceAddr` list

### 2.18.10 InUseInterfaceFlags

**class** cdrouter.system.**InUseInterfaceFlags** (\*\*kwargs)  
Model for CDRouter In Use Interface Flags.

#### Parameters

- **in\_use** – (optional) Bool *True* if interface is in use by a running job.
- **is\_wireless** – (optional) Bool *True* if interface is a wireless interface.
- **is\_ics** – (optional) Bool *True* if interface is in use as the ICS interface of a running job.

### 2.18.11 InUseInterface

**class** cdrouter.system.**InUseInterface** (\*\*kwargs)  
Model for CDRouter In Use Interfaces.

#### Parameters

- **name** – (optional) Interface name as a string.
- **flags** – (optional) `system.InUseInterfaceFlags` object

### 2.18.12 Preferences

**class** cdrouter.system.**Preferences** (\*\*kwargs)  
Model for CDRouter Preferences.

#### Parameters

- **automatic\_login** – (optional) Bool *True* if Automatic Login is enabled.
- **cloudshark\_appliance\_autotags** – (optional) CloudShark Appliance autotags as a string.
- **cloudshark\_appliance\_insecure** – (optional) String *yes* if insecure CloudShark Appliance URLs are allowed.

- **cloudshark\_appliance\_password** – (optional) CloudShark Appliance password as a string.
- **cloudshark\_appliance\_tags** – (optional) CloudShark Appliance tags as a string.
- **cloudshark\_appliance\_token** – (optional) CloudShark Appliance API token as a string.
- **cloudshark\_appliance\_url** – (optional) CloudShark Appliance URL as a string.
- **cloudshark\_appliance\_username** – (optional) CloudShark Appliance username as a string.
- **hostname** – (optional) CDRouter system’s hostname as a string.
- **migrated** – (optional) Migrated resources as a string list.
- **port** – (optional) CDRouter’s HTTP port as an int.
- **https** – (optional) CDRouter’s HTTPS port as an int.
- **force\_https** – (optional) If string *yes*, redirect HTTP connections to CDRouter to HTTPS.
- **use\_cloudshark** – (optional) If string *yes*, use CloudShark Appliance for capture viewing.
- **log\_timestamp\_format** – (optional) Log timestamp format, must be string *short* or *long*.
- **editor\_keymap** – (optional) Config editor keymap, must be string *default*, *emacs* or *vim*.
- **lounge\_url** – (optional) CDRouter Support Lounge URL as a string.
- **lounge\_insecure** – (optional) If bool *True*, allow insecure HTTPS connections to the CDRouter Support Lounge.

### 2.18.13 Space

**class** `cdrouter.system.Space` (*\*\*kwargs*)  
Model for CDRouter Disk Space Usage.

#### Parameters

- **avail** – (optional) Available disk space as an int.
- **path** – (optional) Path to CDRouter’s data directory as a string.
- **pcent** – (optional) Percentage of disk space used as an int.
- **size** – (optional) Total disk space as an int.
- **unit** – (optional) Disk space units as a string, default is ‘bytes’.
- **used** – (optional) Used disk space as an int.

## 2.19 Tags

### 2.19.1 TagsService

**class** `cdrouter.tags.TagsService` (*service*)  
Service for accessing CDRouter Tags.

**delete** (*name*)

Delete a tag.

**Parameters** **name** – Tag name as string.

**edit** (*resource*, *old\_name=None*)

Edit a tag. When renaming a tag, *old\_name* must be set to the old tag name.

**Parameters**

- **resource** – `tags.Tag` object
- **old\_name** – (optional) Old tag name as a string. Only required when renaming a tag.

**Returns** `tags.Tag` object

**Return type** *tags.Tag*

**get** (*name*)

Get a tag.

**Parameters** **name** – Tag name as string.

**Returns** `tags.Tag` object

**Return type** *tags.Tag*

**list** (*resource=None*, *sort=None*)

Get a list of tags.

**Parameters**

- **resource** – (optional) Restrict to given resource type as string.
- **sort** – (optional) Sort fields to apply as string list.

**Returns** `tags.Tag` list

## 2.19.2 Tag

**class** `cdrouter.tags.Tag` (*\*\*kwargs*)

Model for CDRouter Tags.

**Parameters**

- **resource** – (optional) Resource type as string.
- **id** – (optional) Resource ID as an int.
- **name** – (optional) Resource name as string.
- **count** – (optional) Resource tag count as an int.
- **tags** – (optional) Resource tags as a string list.
- **configs** – (optional) `tags.ResourceTags` list
- **devices** – (optional) `tags.ResourceTags` list
- **packages** – (optional) `tags.ResourceTags` list
- **results** – (optional) `tags.ResourceTags` list

## 2.19.3 ResourceTags

**class** `cdrouter.tags.ResourceTags` (*\*\*kwargs*)  
Model for CDRouter Resource Tags.

**Parameters**

- **id** – (optional) Resource ID as an int.
- **name** – (optional) Resource name as string.
- **tags** – (optional) Resource tags as a string list.

## 2.20 Testsuites

### 2.20.1 TestsuitesService

**class** `cdrouter.testsuites.TestsuitesService` (*service*)  
Service for accessing CDRouter Testsuites.

**get\_error** (*name*)  
Get an error.

**Parameters** **name** – Error name as string.

**Returns** `testsuites.Error` object

**Return type** *testsuites.Error*

**get\_group** (*name*)  
Get a group.

**Parameters** **name** – Group name as string.

**Returns** `testsuites.Group` object

**Return type** *testsuites.Group*

**get\_label** (*name*)  
Get a label.

**Parameters** **name** – Label name as string.

**Returns** `testsuites.Label` object

**Return type** *testsuites.Label*

**get\_module** (*name*)  
Get a module.

**Parameters** **name** – Module name as string.

**Returns** `testsuites.Module` object

**Return type** *testsuites.Module*

**get\_test** (*name*)  
Get a test.

**Parameters** **name** – Test name as string.

**Returns** `testsuites.Test` object

**Return type** *testsuites.Test*



**get\_testvar** (*name*)

Get a testvar.

**Parameters** **name** – Testvar name as string.

**Returns** `testsuites.Testvar` object

**Return type** *testsuites.Testvar*

**info** ()

Get testsuite info.

**Returns** `testsuites.Info` object

**Return type** *testsuites.Info*

**list\_errors** (*filter=None, type=None, sort=None, detailed=None*)

Get a list of errors.

**Parameters**

- **filter** – (optional) Filters to apply as a string list.
- **type** – (optional) *union* or *inter* as string.
- **sort** – (optional) Sort fields to apply as string list.
- **detailed** – (optional) Return all fields if Bool *True*.

**Returns** `testsuites.Error` list

**list\_groups** (*filter=None, type=None, sort=None, detailed=None*)

Get a list of groups.

**Parameters**

- **filter** – (optional) Filters to apply as a string list.
- **type** – (optional) *union* or *inter* as string.
- **sort** – (optional) Sort fields to apply as string list.
- **detailed** – (optional) Return all fields if Bool *True*.

**Returns** `testsuites.Group` list

**list\_labels** (*filter=None, type=None, sort=None, detailed=None*)

Get a list of labels.

**Parameters**

- **filter** – (optional) Filters to apply as a string list.
- **type** – (optional) *union* or *inter* as string.
- **sort** – (optional) Sort fields to apply as string list.
- **detailed** – (optional) Return all fields if Bool *True*.

**Returns** `testsuites.Label` list

**list\_modules** (*filter=None, type=None, sort=None, detailed=None*)

Get a list of modules.

**Parameters**

- **filter** – (optional) Filters to apply as a string list.
- **type** – (optional) *union* or *inter* as string.

- **sort** – (optional) Sort fields to apply as string list.
- **detailed** – (optional) Return all fields if Bool *True*.

**Returns** `testsuites.Module` list

**list\_tests** (*filter=None, type=None, sort=None, detailed=None*)  
Get a list of tests.

**Parameters**

- **filter** – (optional) Filters to apply as a string list.
- **type** – (optional) *union* or *inter* as string.
- **sort** – (optional) Sort fields to apply as string list.
- **detailed** – (optional) Return all fields if Bool *True*.

**Returns** `testsuites.Test` list

**list\_testvars** (*filter=None, type=None, sort=None, detailed=None*)  
Get a list of testvars.

**Parameters**

- **filter** – (optional) Filters to apply as a string list.
- **type** – (optional) *union* or *inter* as string.
- **sort** – (optional) Sort fields to apply as string list.
- **detailed** – (optional) Return all fields if Bool *True*.

**Returns** `testsuites.Testvar` list

**search** (*query*)  
Perform full text search of testsuite.

**Parameters** **query** – Search query as a string.

**Returns** `testsuites.Search` object

**Return type** `testsuites.Search`

**update** ()  
Update testsuite info.

## 2.20.2 Info

**class** `cdrouter.testsuites.Info` (*\*\*kwargs*)  
Model for CDRouter Testsuite Info.

**Parameters**

- **id** – (optional) Testsuite ID as an int.
- **build\_info** – (optional) CDRouter build info as string.
- **copyright** – (optional) CDRouter copyright info as string.
- **license\_type** – (optional) License type as string.
- **customer** – (optional) Customer name from license as string.
- **lifetime** – (optional) License lifetime as string.
- **killtime** – (optional) License killtime as string.

- **nag** – (optional) Bool *True* if should nag leading up to license expiration.
- **os** – (optional) OS name as string.
- **os\_type** – (optional) OS type as string.
- **serial\_number** – (optional) NTA serial number as string.
- **system\_id** – (optional) CDRouter system ID as string.
- **testsuite** – (optional) CDRouter testsuite name as string.
- **release** – (optional) CDRouter release as string.
- **addons** – (optional) Enabled CDRouter addons as string list.
- **all\_addons** – (optional) All CDRouter addons as string list.
- **interfaces** – (optional) `configs.Interfaces` list
- **execute\_instances** – (optional) Execute instances as an int.
- **license\_info** – (optional) `testsuites.LicenseInfo` object

### 2.20.3 Group

**class** `cdrouter.testsuites.Group` (*\*\*kwargs*)  
Model for CDRouter Groups.

#### Parameters

- **id** – (optional) Testsuite ID as an int.
- **name** – (optional) Name as string.
- **index** – (optional) Index as int.
- **test\_count** – (optional) Test count as int.
- **modules** – (optional) Modules as string list.

### 2.20.4 Module

**class** `cdrouter.testsuites.Module` (*\*\*kwargs*)  
Model for CDRouter Modules.

#### Parameters

- **id** – (optional) Testsuite ID as an int.
- **name** – (optional) Name as string.
- **index** – (optional) Index as int.
- **group** – (optional) Group name as string.
- **description** – (optional) Module description as string.
- **test\_count** – (optional) Test count as int.
- **tests** – (optional) Tests as string list.
- **labels** – (optional) Labels as string list.
- **aliases** – (optional) Aliases as string list.

### 2.20.5 Test

**class** `cdrouter.testsuites.Test` (*\*\*kwargs*)  
Model for CDRouter Tests.

#### Parameters

- **id** – (optional) Testsuite ID as an int.
- **name** – (optional) Name as string.
- **index** – (optional) Index as int.
- **group** – (optional) Group name as string.
- **module** – (optional) Module name as string.
- **synopsis** – (optional) Test synopsis as string.
- **description** – (optional) Test description as string.
- **labels** – (optional) Labels as string list.
- **aliases** – (optional) Aliases as string list.
- **testvars** – (optional) Testvars as string list.
- **skip\_name** – (optional) Skip name as string.
- **skip\_reason** – (optional) Skip reason as string.

### 2.20.6 Label

**class** `cdrouter.testsuites.Label` (*\*\*kwargs*)  
Model for CDRouter Skip Labels.

#### Parameters

- **id** – (optional) Testsuite ID as an int.
- **name** – (optional) Name as string.
- **index** – (optional) Index as int.
- **reason** – (optional) Skip reason as string.
- **description** – (optional) Description as string.
- **modules** – (optional) Modules as string list.
- **tests** – (optional) Tests as string list.

### 2.20.7 Error

**class** `cdrouter.testsuites.Error` (*\*\*kwargs*)  
Model for CDRouter Start Errors.

#### Parameters

- **id** – (optional) Testsuite ID as an int.
- **name** – (optional) Name as string.
- **index** – (optional) Index as int.

- **description** – (optional) Description as string.

## 2.20.8 Testvar

**class** cdrouter.testsuites.**Testvar** (\*\*kwargs)

Model for CDRouter Start Errors.

### Parameters

- **id** – (optional) Testsuite ID as an int.
- **name** – (optional) Name as a string.
- **index** – (optional) Index as an int.
- **humanname** – (optional) Human-readable name as a string.
- **display** – (optional) Display name as a string.
- **dataclass** – (optional) Data-type as a string.
- **addedin** – (optional) Added-in info as a string.
- **deprecatedin** – (optional) Deprecated-in info as a string.
- **obsoletedin** – (optional) Obsoleted-in info as a string.
- **min** – (optional) Minimum value as a string.
- **max** – (optional) Maximum value as a string.
- **length** – (optional) Required length as a string.
- **description** – (optional) Description as a string.
- **default** – (optional) Default value as a string.
- **defaultdisabled** – (optional) Bool *True* if testvar has no default value.
- **dyndefault** – (optional) Bool *True* if testvar's default value is dynamically calculated.
- **keywords** – (optional) Accepted values as a string list.
- **alsoaccept** – (optional) Also-accepted values as a string list.
- **wildcard** – (optional) Bool *True* if testvar is a wildcard testvar.
- **instances** – (optional) Number of allowed wildcard instances as an int.
- **parent** – (optional) Parent wildcard testvar name as a string.
- **children** – (optional) Child testvars as a string list.
- **tests** – (optional) Test names as a string list.

## 2.20.9 Search

**class** cdrouter.testsuites.**Search** (\*\*kwargs)

Model for CDRouter Testsuite Searches.

### Parameters

- **addons** – (optional) testsuites.Group list
- **modules** – (optional) testsuites.Module list

- **tests** – (optional) `testsuites.Test` list
- **reasons** – (optional) `testsuites.Label` list
- **errors** – (optional) `testsuites.Error` list
- **testvars** – (optional) `testsuites.Testvar` list

## 2.21 Users

### 2.21.1 UsersService

**class** `cdrouter.users.UsersService` (*service*)

Service for accessing CDRouter Users.

**bulk\_copy** (*ids*)

Bulk copy a set of users.

**Parameters** **ids** – Int list of user IDs.

**Returns** `users.User` list

**bulk\_delete** (*ids=None, filter=None, type=None, all=False*)

Bulk delete a set of users.

**Parameters**

- **ids** – (optional) Int list of user IDs.
- **filter** – (optional) String list of filters.
- **type** – (optional) *union* or *inter* as string.
- **all** – (optional) Apply to all if bool *True*.

**bulk\_edit** (*\_fields, ids=None, filter=None, type=None, all=False*)

Bulk edit a set of users.

**Parameters**

- **\_fields** – `users.User` object
- **ids** – (optional) Int list of user IDs.
- **filter** – (optional) String list of filters.
- **type** – (optional) *union* or *inter* as string.
- **all** – (optional) Apply to all if bool *True*.

**change\_password** (*id, new, old=None, change\_token=True*)

Change a user's password.

**Parameters**

- **id** – User ID as an int.
- **new** – New password as string.
- **old** – (optional) Old password as string (required if performing action as non-admin).
- **change\_token** – (optional) If bool *True*, also generate a new API token for user.

**Returns** `users.User` object

**Return type** *users.User*

**change\_token** (*id*)

Change a user's token.

**Parameters** *id* – User ID as an int.

**Returns** *users.User* object

**Return type** *users.User*

**create** (*resource*)

Create a new user.

**Parameters** *resource* – *users.User* object

**Returns** *users.User* object

**Return type** *users.User*

**delete** (*id*)

Delete a user.

**Parameters** *id* – User ID as an int.

**edit** (*resource*)

Edit a user.

**Parameters** *resource* – *users.User* object

**Returns** *users.User* object

**Return type** *users.User*

**get** (*id*)

Get a user.

**Parameters** *id* – User ID as an int.

**Returns** *users.User* object

**Return type** *users.User*

**get\_by\_name** (*name*)

Get a user by name.

**Parameters** *name* – User name as string.

**Returns** *users.User* object

**Return type** *users.User*

**iter\_list** (*\*args, \*\*kwargs*)

Get a list of users. Whereas *list* fetches a single page of users according to its *limit* and *page* arguments, *iter\_list* returns all users by internally making successive calls to *list*.

**Parameters**

- **args** – Arguments that *list* takes.
- **kwargs** – Optional arguments that *list* takes.

**Returns** *users.User* list

**list** (*filter=None, type=None, sort=None, limit=None, page=None, detailed=None*)

Get a list of users, using summary representation by default (see *detailed* parameter).

**Parameters**

- **filter** – (optional) Filters to apply as a string list.
- **type** – (optional) *union* or *inter* as string.
- **sort** – (optional) Sort fields to apply as string list.
- **limit** – (optional) Limit returned list length.
- **page** – (optional) Page to return.
- **detailed** – (optional) Return all fields if Bool *True*.

**Returns** `users.Page` object

**lock** (*id*)

Lock a user. Locking prevents the user from being modified or deleted until it is unlocked.

**Parameters** **id** – User ID as an int.

**Returns** `users.User` object

**Return type** *users.User*

**unlock** (*id*)

Unlock a user. Unlocking a locked user allows it to be modified or deleted once again.

**Parameters** **id** – User ID as an int.

**Returns** `users.User` object

**Return type** *users.User*

## 2.21.2 User

**class** `cdrouter.users.User` (*\*\*kwargs*)

Model for CDRouter Users.

**Parameters**

- **id** – (optional) User ID as an int.
- **admin** – (optional) Bool *True* if user is an administrator.
- **disabled** – (optional) Bool *True* if user is disabled.
- **name** – (optional) User name as string.
- **description** – (optional) User description as string.
- **created** – (optional) User creation time as *DateTime*.
- **updated** – (optional) User last-updated time as *DateTime*.
- **locked** – (optional) Bool *True* if user is locked.
- **token** – (optional) User's API token as string.

## 2.21.3 Page

**class** `cdrouter.users.Page`

Named tuple for a page of list response data.

**Parameters**

- **data** – `users.User` list



- **links** – `cdrouter.Links` object



**C**

`cdrouter`, 3



## A

AddrCount (class in *cdrouter.alerts*), 44  
 Alert (class in *cdrouter.alerts*), 42  
 alerts (*cdrouter.CDRouter* attribute), 4  
 AlertsService (class in *cdrouter.alerts*), 41  
 all\_stats() (*cdrouter.alerts.AlertsService* method), 41  
 all\_stats() (*cdrouter.results.ResultsService* method), 29  
 AllStats (class in *cdrouter.alerts*), 44  
 AllStats (class in *cdrouter.results*), 38  
 Analysis (class in *cdrouter.packages*), 28  
 analyze() (*cdrouter.packages.PackagesService* method), 24  
 Annotation (class in *cdrouter.annotations*), 51  
 annotations (*cdrouter.CDRouter* attribute), 4  
 AnnotationsService (class in *cdrouter.annotations*), 49  
 Attachment (class in *cdrouter.attachments*), 20  
 attachments (*cdrouter.CDRouter* attribute), 4  
 AttachmentsService (class in *cdrouter.attachments*), 19  
 authenticate() (*cdrouter.CDRouter* method), 4

## B

Bandwidth (class in *cdrouter.metrics*), 51  
 bulk\_copy() (*cdrouter.configs.ConfigsService* method), 8  
 bulk\_copy() (*cdrouter.devices.DevicesService* method), 14  
 bulk\_copy() (*cdrouter.packages.PackagesService* method), 24  
 bulk\_copy() (*cdrouter.users.UsersService* method), 74  
 bulk\_delete() (*cdrouter.configs.ConfigsService* method), 8  
 bulk\_delete() (*cdrouter.devices.DevicesService* method), 14  
 bulk\_delete() (*cdrouter.jobs.JobsService* method),

21

bulk\_delete() (*cdrouter.packages.PackagesService* method), 24  
 bulk\_delete() (*cdrouter.results.ResultsService* method), 29  
 bulk\_delete() (*cdrouter.users.UsersService* method), 74  
 bulk\_edit() (*cdrouter.configs.ConfigsService* method), 8  
 bulk\_edit() (*cdrouter.devices.DevicesService* method), 14  
 bulk\_edit() (*cdrouter.packages.PackagesService* method), 24  
 bulk\_edit() (*cdrouter.results.ResultsService* method), 29  
 bulk\_edit() (*cdrouter.users.UsersService* method), 74  
 bulk\_edit\_testvars() (*cdrouter.configs.ConfigsService* method), 8  
 bulk\_export() (*cdrouter.configs.ConfigsService* method), 8  
 bulk\_export() (*cdrouter.devices.DevicesService* method), 15  
 bulk\_export() (*cdrouter.exports.ExportsService* method), 59  
 bulk\_export() (*cdrouter.packages.PackagesService* method), 24  
 bulk\_export() (*cdrouter.results.ResultsService* method), 29  
 bulk\_launch() (*cdrouter.jobs.JobsService* method), 21  
 bulk\_upgrade() (*cdrouter.configs.ConfigsService* method), 8

## C

Capture (class in *cdrouter.captures*), 55  
 captures (*cdrouter.CDRouter* attribute), 4  
 CapturesService (class in *cdrouter.captures*), 54  
 CategoryCount (class in *cdrouter.alerts*), 43

`CDRouter` (class in `cdrouter`), 3  
`cdrouter` (module), 3  
`CDRouterError` (class in `cdrouter.cdrouter`), 5  
`change_password()` (`cdrouter.users.UsersService` method), 74  
`change_token()` (`cdrouter.users.UsersService` method), 75  
`check_config()` (`cdrouter.configs.ConfigsService` method), 9  
`check_for_lounge_upgrade()` (`cdrouter.system.SystemService` method), 61  
`CheckConfig` (class in `cdrouter.configs`), 13  
`ClientBandwidth` (class in `cdrouter.metrics`), 52  
`ClientLatency` (class in `cdrouter.metrics`), 52  
`CloudShark` (class in `cdrouter.captures`), 55  
`commit()` (`cdrouter.imports.ImportsService` method), 57  
`Config` (class in `cdrouter.configs`), 12  
`ConfigError` (class in `cdrouter.configs`), 13  
`configs` (`cdrouter.CDRouter` attribute), 4  
`ConfigsService` (class in `cdrouter.configs`), 8  
`connect()` (`cdrouter.devices.DevicesService` method), 15  
`Connection` (class in `cdrouter.devices`), 19  
`contained_by()` (`cdrouter.filters.Field` method), 6  
`contains()` (`cdrouter.filters.Field` method), 6  
`create()` (`cdrouter.annotations.AnnotationsService` method), 49  
`create()` (`cdrouter.attachments.AttachmentsService` method), 19  
`create()` (`cdrouter.configs.ConfigsService` method), 9  
`create()` (`cdrouter.devices.DevicesService` method), 15  
`create()` (`cdrouter.highlights.HighlightsService` method), 55  
`create()` (`cdrouter.packages.PackagesService` method), 25  
`create()` (`cdrouter.users.UsersService` method), 75  
`create_or_edit()` (`cdrouter.annotations.AnnotationsService` method), 50  
`create_or_edit()` (`cdrouter.highlights.HighlightsService` method), 55  
`create_testvar_group()` (`cdrouter.configs.ConfigsService` method), 9

## D

`delete()` (`cdrouter.annotations.AnnotationsService` method), 50  
`delete()` (`cdrouter.attachments.AttachmentsService` method), 19  
`delete()` (`cdrouter.configs.ConfigsService` method), 9

`delete()` (`cdrouter.devices.DevicesService` method), 15  
`delete()` (`cdrouter.highlights.HighlightsService` method), 55  
`delete()` (`cdrouter.imports.ImportsService` method), 57  
`delete()` (`cdrouter.jobs.JobsService` method), 21  
`delete()` (`cdrouter.packages.PackagesService` method), 25  
`delete()` (`cdrouter.results.ResultsService` method), 29  
`delete()` (`cdrouter.tags.TagsService` method), 66  
`delete()` (`cdrouter.users.UsersService` method), 75  
`delete_testvar()` (`cdrouter.configs.ConfigsService` method), 9  
`delete_testvar_group()` (`cdrouter.configs.ConfigsService` method), 9  
`Device` (class in `cdrouter.devices`), 17  
`DeviceCount` (class in `cdrouter.results`), 38  
`devices` (`cdrouter.CDRouter` attribute), 4  
`DevicesService` (class in `cdrouter.devices`), 14  
`diagnostics()` (`cdrouter.system.SystemService` method), 61  
`diff_stats()` (`cdrouter.results.ResultsService` method), 29  
`DiffStats` (class in `cdrouter.results`), 37  
`disconnect()` (`cdrouter.devices.DevicesService` method), 15  
`download()` (`cdrouter.attachments.AttachmentsService` method), 19  
`download()` (`cdrouter.captures.CapturesService` method), 54  
`download_logdir_archive()` (`cdrouter.results.ResultsService` method), 29

## E

`edit()` (`cdrouter.annotations.AnnotationsService` method), 50  
`edit()` (`cdrouter.attachments.AttachmentsService` method), 19  
`edit()` (`cdrouter.configs.ConfigsService` method), 9  
`edit()` (`cdrouter.devices.DevicesService` method), 15  
`edit()` (`cdrouter.highlights.HighlightsService` method), 56  
`edit()` (`cdrouter.jobs.JobsService` method), 22  
`edit()` (`cdrouter.packages.PackagesService` method), 25  
`edit()` (`cdrouter.results.ResultsService` method), 30  
`edit()` (`cdrouter.tags.TagsService` method), 67  
`edit()` (`cdrouter.testresults.TestResultsService` method), 44  
`edit()` (`cdrouter.users.UsersService` method), 75

`edit_preferences()` (*cdrouter.system.SystemService method*), 61  
`edit_shares()` (*cdrouter.configs.ConfigsService method*), 10  
`edit_shares()` (*cdrouter.devices.DevicesService method*), 15  
`edit_shares()` (*cdrouter.packages.PackagesService method*), 25  
`edit_shares()` (*cdrouter.results.ResultsService method*), 30  
`edit_testvar()` (*cdrouter.configs.ConfigsService method*), 10  
`eq()` (*cdrouter.filters.Field method*), 6  
`Error` (class in *cdrouter.testsuites*), 72  
`export()` (*cdrouter.configs.ConfigsService method*), 10  
`export()` (*cdrouter.devices.DevicesService method*), 15  
`export()` (*cdrouter.packages.PackagesService method*), 25  
`export()` (*cdrouter.results.ResultsService method*), 30  
`exports` (*cdrouter.CDRouter attribute*), 4  
`ExportsService` (class in *cdrouter.exports*), 59

## F

`Feature` (class in *cdrouter.results*), 39  
`Field` (class in *cdrouter.filters*), 5

## G

`ge()` (*cdrouter.filters.Field method*), 6  
`get()` (*cdrouter.alerts.AlertsService method*), 41  
`get()` (*cdrouter.annotations.AnnotationsService method*), 50  
`get()` (*cdrouter.attachments.AttachmentsService method*), 19  
`get()` (*cdrouter.captures.CapturesService method*), 54  
`get()` (*cdrouter.configs.ConfigsService method*), 10  
`get()` (*cdrouter.devices.DevicesService method*), 15  
`get()` (*cdrouter.highlights.HighlightsService method*), 56  
`get()` (*cdrouter.imports.ImportsService method*), 57  
`get()` (*cdrouter.jobs.JobsService method*), 22  
`get()` (*cdrouter.packages.PackagesService method*), 25  
`get()` (*cdrouter.results.ResultsService method*), 30  
`get()` (*cdrouter.tags.TagsService method*), 67  
`get()` (*cdrouter.testresults.TestResultsService method*), 44  
`get()` (*cdrouter.users.UsersService method*), 75  
`get_by_name()` (*cdrouter.configs.ConfigsService method*), 10  
`get_by_name()` (*cdrouter.devices.DevicesService method*), 16  
`get_by_name()` (*cdrouter.packages.PackagesService method*), 25  
`get_by_name()` (*cdrouter.users.UsersService method*), 75  
`get_commit_request()` (*cdrouter.imports.ImportsService method*), 57  
`get_connection()` (*cdrouter.devices.DevicesService method*), 16  
`get_error()` (*cdrouter.testsuites.TestsuitesService method*), 68  
`get_group()` (*cdrouter.testsuites.TestsuitesService method*), 68  
`get_interfaces()` (*cdrouter.configs.ConfigsService method*), 10  
`get_interfaces()` (*cdrouter.jobs.JobsService method*), 22  
`get_interfaces()` (*cdrouter.packages.PackagesService method*), 25  
`get_label()` (*cdrouter.testsuites.TestsuitesService method*), 68  
`get_log_plaintext()` (*cdrouter.testresults.TestResultsService method*), 45  
`get_logdir_file()` (*cdrouter.results.ResultsService method*), 30  
`get_module()` (*cdrouter.testsuites.TestsuitesService method*), 68  
`get_networks()` (*cdrouter.configs.ConfigsService method*), 10  
`get_new()` (*cdrouter.configs.ConfigsService method*), 10  
`get_plaintext()` (*cdrouter.configs.ConfigsService method*), 11  
`get_preferences()` (*cdrouter.system.SystemService method*), 61  
`get_shares()` (*cdrouter.configs.ConfigsService method*), 11  
`get_shares()` (*cdrouter.devices.DevicesService method*), 16  
`get_shares()` (*cdrouter.packages.PackagesService method*), 25  
`get_shares()` (*cdrouter.results.ResultsService method*), 30  
`get_test()` (*cdrouter.testsuites.TestsuitesService method*), 68  
`get_test_metric()` (*cdrouter.results.ResultsService method*), 30  
`get_test_metric()` (*cdrouter.testresults.TestResultsService method*), 45  
`get_test_metric_csv()` (*cdrouter.results.ResultsService method*), 31  
`get_test_metric_csv()` (*cdrouter.testresults.TestResultsService method*), 45

method), 45  
get\_testvar() (cdrouter.configs.ConfigsService method), 11  
get\_testvar() (cdrouter.testsuites.TestsuitesService method), 68  
GraphMetric (class in cdrouter.metrics), 52  
Group (class in cdrouter.testsuites), 71  
gt() (cdrouter.filters.Field method), 6

## H

Highlight (class in cdrouter.highlights), 56  
highlights (cdrouter.CDRouter attribute), 4  
HighlightsService (class in cdrouter.highlights), 55  
history (cdrouter.CDRouter attribute), 4  
History (class in cdrouter.history), 60  
HistoryService (class in cdrouter.history), 60  
hostname() (cdrouter.system.SystemService method), 61

## I

Import (class in cdrouter.imports), 58  
imports (cdrouter.CDRouter attribute), 4  
ImportsService (class in cdrouter.imports), 57  
in\_use\_interfaces() (cdrouter.system.SystemService method), 61  
Info (class in cdrouter.testsuites), 70  
info() (cdrouter.system.SystemService method), 61  
info() (cdrouter.testsuites.TestsuitesService method), 69  
Interface (class in cdrouter.system), 65  
InterfaceAddr (class in cdrouter.system), 64  
InterfaceFlags (class in cdrouter.system), 64  
Interfaces (class in cdrouter.configs), 13  
interfaces() (cdrouter.system.SystemService method), 61  
InUseInterface (class in cdrouter.system), 65  
InUseInterfaceFlags (class in cdrouter.system), 65  
iter\_list() (cdrouter.alerts.AlertsService method), 41  
iter\_list() (cdrouter.attachments.AttachmentsService method), 20  
iter\_list() (cdrouter.configs.ConfigsService method), 11  
iter\_list() (cdrouter.devices.DevicesService method), 16  
iter\_list() (cdrouter.history.HistoryService method), 60  
iter\_list() (cdrouter.jobs.JobsService method), 22  
iter\_list() (cdrouter.packages.PackagesService method), 26

iter\_list() (cdrouter.results.ResultsService method), 31  
iter\_list() (cdrouter.testresults.TestResultsService method), 45  
iter\_list() (cdrouter.users.UsersService method), 75  
iter\_list\_log() (cdrouter.testresults.TestResultsService method), 46

## J

Job (class in cdrouter.jobs), 23  
jobs (cdrouter.CDRouter attribute), 4  
JobsService (class in cdrouter.jobs), 21

## L

Label (class in cdrouter.testsuites), 72  
Latency (class in cdrouter.metrics), 53  
latest\_lounge\_release() (cdrouter.system.SystemService method), 62  
launch() (cdrouter.jobs.JobsService method), 22  
le() (cdrouter.filters.Field method), 7  
Line (class in cdrouter.testresults), 48  
Links (class in cdrouter.cdrouter), 5  
list() (cdrouter.alerts.AlertsService method), 41  
list() (cdrouter.annotations.AnnotationsService method), 50  
list() (cdrouter.attachments.AttachmentsService method), 20  
list() (cdrouter.captures.CapturesService method), 54  
list() (cdrouter.configs.ConfigsService method), 11  
list() (cdrouter.devices.DevicesService method), 16  
list() (cdrouter.highlights.HighlightsService method), 56  
list() (cdrouter.history.HistoryService method), 60  
list() (cdrouter.imports.ImportsService method), 57  
list() (cdrouter.jobs.JobsService method), 22  
list() (cdrouter.packages.PackagesService method), 26  
list() (cdrouter.results.ResultsService method), 31  
list() (cdrouter.tags.TagsService method), 67  
list() (cdrouter.testresults.TestResultsService method), 46  
list() (cdrouter.users.UsersService method), 75  
list\_csv() (cdrouter.results.ResultsService method), 31  
list\_csv() (cdrouter.testresults.TestResultsService method), 46  
list\_errors() (cdrouter.testsuites.TestsuitesService method), 69  
list\_groups() (cdrouter.testsuites.TestsuitesService method), 69  
list\_labels() (cdrouter.testsuites.TestsuitesService method), 69



[list\\_log\(\)](#) (*cdrouter.testresults.TestResultsService method*), 46  
[list\\_logdir\(\)](#) (*cdrouter.results.ResultsService method*), 32  
[list\\_metrics\(\)](#) (*cdrouter.results.ResultsService method*), 32  
[list\\_metrics\(\)](#) (*cdrouter.testresults.TestResultsService method*), 47  
[list\\_modules\(\)](#) (*cdrouter.testsuites.TestsuitesService method*), 69  
[list\\_tests\(\)](#) (*cdrouter.testsuites.TestsuitesService method*), 70  
[list\\_testvars\(\)](#) (*cdrouter.configs.ConfigsService method*), 11  
[list\\_testvars\(\)](#) (*cdrouter.testsuites.TestsuitesService method*), 70  
[lock\(\)](#) (*cdrouter.configs.ConfigsService method*), 11  
[lock\(\)](#) (*cdrouter.devices.DevicesService method*), 16  
[lock\(\)](#) (*cdrouter.packages.PackagesService method*), 26  
[lock\(\)](#) (*cdrouter.results.ResultsService method*), 32  
[lock\(\)](#) (*cdrouter.users.UsersService method*), 76  
[Log](#) (*class in cdrouter.testresults*), 49  
[LogDirFile](#) (*class in cdrouter.results*), 38  
[lounge\\_update\\_license\(\)](#) (*cdrouter.system.SystemService method*), 62  
[lounge\\_upgrade\(\)](#) (*cdrouter.system.SystemService method*), 62  
[lt\(\)](#) (*cdrouter.filters.Field method*), 7

## M

[manual\\_update\\_license\(\)](#) (*cdrouter.system.SystemService method*), 62  
[manual\\_upgrade\(\)](#) (*cdrouter.system.SystemService method*), 62  
[match\(\)](#) (*cdrouter.filters.Field method*), 7  
[Metric](#) (*class in cdrouter.metrics*), 53  
[Module](#) (*class in cdrouter.testsuites*), 71

## N

[ne\(\)](#) (*cdrouter.filters.Field method*), 7  
[Networks](#) (*class in cdrouter.configs*), 13  
[not\\_\(\)](#) (*cdrouter.filters.Field method*), 7

## O

[Options](#) (*class in cdrouter.jobs*), 23  
[Options](#) (*class in cdrouter.packages*), 27  
[Options](#) (*class in cdrouter.results*), 39  
[overlaps\(\)](#) (*cdrouter.filters.Field method*), 7

## P

[Package](#) (*class in cdrouter.packages*), 27  
[PackageCount](#) (*class in cdrouter.results*), 38  
[packages](#) (*cdrouter.CDRouter attribute*), 4  
[PackagesService](#) (*class in cdrouter.packages*), 24  
[Page](#) (*class in cdrouter.alerts*), 42  
[Page](#) (*class in cdrouter.attachments*), 21  
[Page](#) (*class in cdrouter.configs*), 12  
[Page](#) (*class in cdrouter.devices*), 18  
[Page](#) (*class in cdrouter.history*), 61  
[Page](#) (*class in cdrouter.jobs*), 24  
[Page](#) (*class in cdrouter.metrics*), 53  
[Page](#) (*class in cdrouter.packages*), 28  
[Page](#) (*class in cdrouter.results*), 35  
[Page](#) (*class in cdrouter.testresults*), 48  
[Page](#) (*class in cdrouter.users*), 76  
[pause\(\)](#) (*cdrouter.results.ResultsService method*), 32  
[pause\\_end\\_of\\_loop\(\)](#) (*cdrouter.results.ResultsService method*), 32  
[pause\\_end\\_of\\_test\(\)](#) (*cdrouter.results.ResultsService method*), 32  
[power\\_off\(\)](#) (*cdrouter.devices.DevicesService method*), 17  
[power\\_on\(\)](#) (*cdrouter.devices.DevicesService method*), 17  
[PowerCmd](#) (*class in cdrouter.devices*), 18  
[poweroff\(\)](#) (*cdrouter.system.SystemService method*), 62  
[Preferences](#) (*class in cdrouter.system*), 65  
[Progress](#) (*class in cdrouter.results*), 37  
[progress\\_stats\(\)](#) (*cdrouter.results.ResultsService method*), 33

## R

[reboot\(\)](#) (*cdrouter.system.SystemService method*), 62  
[Release](#) (*class in cdrouter.system*), 64  
[ReleaseLatest](#) (*class in cdrouter.system*), 63  
[Request](#) (*class in cdrouter.imports*), 59  
[Resource](#) (*class in cdrouter.imports*), 59  
[ResourceTags](#) (*class in cdrouter.tags*), 68  
[Response](#) (*class in cdrouter.imports*), 58  
[restart\(\)](#) (*cdrouter.system.SystemService method*), 62  
[Result](#) (*class in cdrouter.results*), 34, 39  
[ResultBreakdown](#) (*class in cdrouter.results*), 36  
[results](#) (*cdrouter.CDRouter attribute*), 4  
[ResultsService](#) (*class in cdrouter.results*), 29  
[RuleSetCount](#) (*class in cdrouter.alerts*), 43

## S

[Schedule](#) (*class in cdrouter.packages*), 28  
[Search](#) (*class in cdrouter.testsuites*), 73  
[search\(\)](#) (*cdrouter.testsuites.TestsuitesService method*), 70

[send\\_to\\_cloudshark\(\)](#)  
     ([cdrouter.captures.CapturesService](#) method),  
     54  
[set\\_stats\(\)](#) ([cdrouter.results.ResultsService](#)  
     method), 33  
[SetStats](#) (class in [cdrouter.results](#)), 36  
[SeverityCount](#) (class in [cdrouter.alerts](#)), 43  
[Share](#) (class in [cdrouter.cdrouter](#)), 5  
[shutdown\(\)](#) ([cdrouter.system.SystemService](#) method),  
     63  
[SignatureCount](#) (class in [cdrouter.alerts](#)), 43  
[single\\_stats\(\)](#) ([cdrouter.results.ResultsService](#)  
     method), 33  
[SingleStats](#) (class in [cdrouter.results](#)), 37  
[Space](#) (class in [cdrouter.system](#)), 66  
[space\(\)](#) ([cdrouter.system.SystemService](#) method), 63  
[stage\\_import\\_from\\_file\(\)](#)  
     ([cdrouter.imports.ImportsService](#) method),  
     57  
[stage\\_import\\_from\\_filesystem\(\)](#)  
     ([cdrouter.imports.ImportsService](#) method),  
     57  
[stage\\_import\\_from\\_url\(\)](#)  
     ([cdrouter.imports.ImportsService](#) method),  
     57  
[stop\(\)](#) ([cdrouter.results.ResultsService](#) method), 33  
[stop\\_end\\_of\\_loop\(\)](#)  
     ([cdrouter.results.ResultsService](#) method),  
     33  
[stop\\_end\\_of\\_test\(\)](#)  
     ([cdrouter.results.ResultsService](#) method),  
     33  
[Summary](#) (class in [cdrouter.testresults](#)), 48  
[summary\\_stats\(\)](#) ([cdrouter.results.ResultsService](#)  
     method), 33  
[SummaryStats](#) (class in [cdrouter.results](#)), 38  
[system](#) ([cdrouter.CDRouter](#) attribute), 4  
[SystemService](#) (class in [cdrouter.system](#)), 61

## T

[Tag](#) (class in [cdrouter.tags](#)), 67  
[tags](#) ([cdrouter.CDRouter](#) attribute), 4  
[TagsService](#) (class in [cdrouter.tags](#)), 66  
[Test](#) (class in [cdrouter.testsuites](#)), 72  
[TestCount](#) (class in [cdrouter.alerts](#)), 44  
[TestCount](#) (class in [cdrouter.results](#)), 35  
[TestDuration](#) (class in [cdrouter.results](#)), 35  
[testlist\\_expanded\(\)](#)  
     ([cdrouter.packages.PackagesService](#) method),  
     26  
[TestResult](#) (class in [cdrouter.testresults](#)), 47  
[TestResultBreakdown](#) (class in [cdrouter.results](#)),  
     37  
[TestResultDiff](#) (class in [cdrouter.results](#)), 37

[TestResultsService](#) (class in [cdrouter.testresults](#)),  
     44  
[TestResultSummary](#) (class in [cdrouter.results](#)), 36  
[tests](#) ([cdrouter.CDRouter](#) attribute), 4  
[Testsuite](#) (class in [cdrouter.system](#)), 63  
[testsuites](#) ([cdrouter.CDRouter](#) attribute), 4  
[TestsuitesService](#) (class in [cdrouter.testsuites](#)), 68  
[Testvar](#) (class in [cdrouter.configs](#)), 14  
[Testvar](#) (class in [cdrouter.testsuites](#)), 73  
[thumbnail\(\)](#) ([cdrouter.attachments.AttachmentsService](#)  
     method), 20  
[time\(\)](#) ([cdrouter.system.SystemService](#) method), 63  
[TimeBreakdown](#) (class in [cdrouter.results](#)), 36

## U

[unlock\(\)](#) ([cdrouter.configs.ConfigsService](#) method), 12  
[unlock\(\)](#) ([cdrouter.devices.DevicesService](#) method),  
     17  
[unlock\(\)](#) ([cdrouter.packages.PackagesService](#)  
     method), 26  
[unlock\(\)](#) ([cdrouter.results.ResultsService](#) method), 33  
[unlock\(\)](#) ([cdrouter.users.UsersService](#) method), 76  
[unpause\(\)](#) ([cdrouter.results.ResultsService](#) method),  
     33  
[Update](#) (class in [cdrouter.results](#)), 39  
[update\(\)](#) ([cdrouter.testsuites.TestsuitesService](#)  
     method), 70  
[updates\(\)](#) ([cdrouter.results.ResultsService](#) method),  
     34  
[Upgrade](#) (class in [cdrouter.system](#)), 64  
[upgrade\\_config\(\)](#) ([cdrouter.configs.ConfigsService](#)  
     method), 12  
[UpgradeConfig](#) (class in [cdrouter.configs](#)), 13  
[User](#) (class in [cdrouter.users](#)), 76  
[users](#) ([cdrouter.CDRouter](#) attribute), 4  
[UsersService](#) (class in [cdrouter.users](#)), 74

## V

[Version](#) (class in [cdrouter.system](#)), 63